

# JAKA

## SDK Manual [Python]

Document Version:     V2.1.14      
SDK Version:     V2.1.14

## Property Description

*All rights reserved by JAKA Robotics Co., Ltd.*

*JAKA Robotics Co., Ltd owns the intellectual property rights of the related technologies contained in the products described in this document.*

This document and related products are distributed under licenses that restrict their use, copy, distribution, and decompilation. Without the prior written authorization of JAKA Robotics Co., Ltd, no part of this product or this document may be copied in any way or in any form.

## Version History

Version NO.	Version Date	Compatible Controller Version	Description
V1.0.0	2020.3.24	V1.4.10/V2.0.10	Create
V1.0.0	2020.6.24	V1.4.10/V2.0.10	Add additional instructions for different motion instructions
V1.0.14	2020.7.24	V1.4.10/V2.0.10	5.61 to 5.64 are new interfaces that modify jog_stop the interface
V1.0.15	2021.04.27	V1.4.24/V1.5.12.17/V2.0.24 and above	Add interfaces 4.69 to 4.110
V1.0.18	2021.08.30	V1.4.24/V1.5.12.17/V2.0.24 and above	Add API use instructions
V2.1.1	2021.12.10	V1.4.24/V1.5.12.17/V2.0.24 and above	Add FTP interface
V2.1.2	2022.07.01	V1.4.24/V1.5.12.17/V2.0.24 and above	Add part of interface and modify the manual structure
V2.1.3	2022.11.29	V1.4.24/V1.5.13.08/V2.0.24 add above	Designation the MoveC circles number
V2.1.7	2024.01.29	V1.5.13.08 and above	Add interfaces of getting and setting the robot installation angle Add interfaces return value -15 Fix the acceleration unit of MoveC Correct the description of upload_file Correct function name of set_status_data_update_time_interval
V2.1.8	2024.3.21	V1.5.13.08 and above	Add API usage instructions to get SDK log path
V2.1.11	2024.4.30	V1.5.13.08 and above	Fix: refine port 10004 communication Fix: fix set_ft_ctrl_frame interface not working Fix: fix for incorrect retransmission of port 10001 commands

V2.1.14	2024.09.30	V1.5.13.08 and above	<p>Fix:</p> <ol style="list-style-type: none"><li>1. Redefined the port 10004 mechanism to solve the SDK crash issue previously caused by port 10004.</li><li>2. Redefined the motion block mechanism to solve the issue that the motion cannot be properly blocked.</li><li>3. Solved the inaccurate positioning issue of the inpos command.</li></ol> <p>Add:</p> <ol style="list-style-type: none"><li>1. Added two new interfaces to set and get system variables: set_user_var(), get_user_var().</li><li>2. Added one new interface to get the information on motion-related status: get_motion_status.</li><li>3. Add some embedded S related interfaces</li></ol> <p>Header file:</p> <ol style="list-style-type: none"><li>1. Updated all the notes of header file to English.</li><li>2. Added copyright and version information at the beginning of the file.</li></ol>
---------	------------	----------------------	--

## Content

<b>1</b>	<b>Introduction.....</b>	<b>5</b>
<b>2</b>	<b>Document Notes .....</b>	<b>5</b>
2.1	Use under Linux.....	5
2.2	Use under Windows.....	5
2.3	Dynamic library version number interrogate method .....	5
<b>3</b>	<b>Data Types.....</b>	<b>6</b>
3.1	IO type .....	6
3.2	Coordinate system type .....	6
3.3	Sport type .....	6
3.4	The return value values.....	6
<b>4</b>	<b>Interface.....</b>	<b>8</b>
4.1	<b>Basic Operation of Robots .....</b>	<b>8</b>
4.1.1	Instantiated robots .....	8
4.1.2	Login.....	8
4.1.3	Logout.....	8
4.1.4	Power on .....	9
4.1.5	Power off.....	9
4.1.6	Shut down robot controller .....	9
4.1.7	Enable the robot.....	10
4.1.8	Disable the robot.....	10
4.1.9	Get SDK Version No.....	10
4.1.10	Get the controller IP .....	11
4.1.11	Enable drag mode .....	11
4.1.12	Interrogate whether in drag mode .....	12
4.1.13	Set whether open SDK debug mode .....	12
4.1.14	Set SDK file path .....	12
4.2	<b>Rove Move .....</b>	<b>12</b>
4.2.1	Control robot movement in manual mode .....	12
4.2.2	Control robot movement stop in manual mode.....	14
4.2.3	Robot joint motion .....	15
4.2.4	Robot extension joint move .....	16
4.2.5	Robot end linear move .....	16
4.2.6	Robot extension end linear move.....	17
4.2.7	Arc movement at the robot end.....	17
4.2.8	Motion abort.....	19
4.2.9	Interrogate whether in position .....	19
4.3	<b>Set and Interrogate Robot Operation Info.....</b>	<b>20</b>
4.3.1	Get robot status (simple).....	20
4.3.2	Get robot status monitor data .....	20
4.3.3	Set robot status data update time interval .....	21
4.3.4	Get joint angles .....	22
4.3.5	Get TCP pose .....	22
4.3.6	Set user coordinate frame parameter.....	23
4.3.7	Get user coordinate frame data .....	23
4.3.8	Get user coordinate frame ID.....	23
4.3.9	Set user coordinate frame ID .....	24
4.3.10	Set the tool information for the specified number.....	24
4.3.11	Set tool ID.....	24
4.3.12	Interrogate target tool coordinate frame ID.....	24
4.3.13	Get the tool ID currently in use.....	25
4.3.14	Set digital output variables.....	25
4.3.15	Set analog output variables .....	26
4.3.16	Get digital input status .....	27
4.3.17	Get digital output status .....	27
4.3.18	Get analog input variables.....	27

4.3.19	Get analog output variables.....	28
4.3.20	Interrogate whether extension IO in running status .....	28
4.3.21	Set payload.....	28
4.3.22	Get payload data .....	29
4.3.23	Set tioV3 parameters.....	29
4.3.24	Get tioV3 parameters .....	29
4.3.25	Get robot status .....	30
4.3.26	TIO add or modify semaphore .....	30
4.3.27	TIO delete semaphore .....	31
4.3.28	TIO RS485 send command .....	31
4.3.29	TIO get semaphore information .....	32
4.3.30	TIO Setting TIO mode .....	32
4.3.31	TIO get TIO mode.....	33
4.3.32	TIO RS485 communication parameter configuration .....	33
4.3.33	TIO RS485 Communication Parameter Query .....	33
4.3.34	TIO RS485 communication mode configuration.....	33
4.3.35	TIO RS485 communication mode configuration.....	34
4.3.36	Set robot installation angle.....	34
4.3.37	Get robot installation angle .....	35
<b>4.4</b>	<b>Robot Safety Status Settings .....</b>	<b>35</b>
4.4.1	Interrogate whether on limit.....	35
4.4.2	Interrogate whether in Collision Protection mode .....	35
4.4.3	Clear the robot error code after collision occur.....	35
4.4.4	Set collision level.....	36
4.4.5	Get collision level .....	37
4.4.6	Get the last error code .....	37
4.4.7	Set error code file path .....	38
4.4.8	Clear error status .....	38
4.4.9	Set the robot automatic move termination types upon network exceptions.....	38
<b>4.5</b>	<b>Use APP Script Program.....</b>	<b>39</b>
4.5.1	Load the specified program.....	39
4.5.2	Get the loaded program.....	39
4.5.3	Get current line .....	40
4.5.4	Run the loaded program .....	40
4.5.5	Pause the running program .....	40
4.5.6	Resume program .....	40
4.5.7	Abort program.....	40
4.5.8	Get program status .....	41
4.5.9	Set rapid rate .....	42
4.5.10	Get rapid rate.....	42
<b>4.6</b>	<b>Trajectory Reproduction .....</b>	<b>42</b>
4.6.1	Set trajectory track configuration parameter.....	42
4.6.2	Get trajectory track configuration parameters.....	43
4.6.3	Set trajectory sample mode .....	43
4.6.4	Get trajectory sample state .....	44
4.6.5	Get exist trajectory file name .....	44
4.6.6	Rename exist trajectory file name.....	44
4.6.7	Remove the trajectory file in the controller .....	44
4.6.8	Generate the trajectory execution script.....	45
<b>4.7</b>	<b>Robot kinematics .....</b>	<b>45</b>
4.7.1	Convert Rpy to rotation matrix .....	45
4.7.2	Convert rotation matrix to rpy .....	45
4.7.3	Convert quaternion to rotation matrix.....	45
4.7.4	Kine inverse .....	46
4.7.5	Kine forward .....	46
4.7.6	Convert rotation matrix to quaternion.....	47
<b>4.8</b>	<b>Robot Servo Mode .....</b>	<b>47</b>
4.8.1	Robot servo move enable.....	47

4.8.2	Robot joint servo move extension.....	47
4.8.3	Robot joint servo move extension.....	49
4.8.4	Cartesian space servo mode .....	50
4.8.5	Robot Cartesian space servo move extension .....	51
4.8.6	None filters in SERVO mode.....	52
4.8.7	Use joint first-order low pass filter in SERVO mode.....	52
4.8.8	Use joint nonlinear filter in SERVO mode.....	52
4.8.9	Use Cartesian space nonlinear filter in SERVO mode .....	53
4.8.10	Use joint multi-order mean filter in SERVO mode.....	53
4.8.11	Set the speed foresight parameters in SERVO mode .....	54
<b>4.9</b>	<b>Force Control Robot Extensions .....</b>	<b>54</b>
4.9.1	Set sensor brand.....	54
4.9.2	Get sensor brand .....	54
4.9.3	Turn on or turn off F/T sensor .....	55
4.9.4	Set compliance control parameters .....	55
4.9.5	Start to identify the tool end payload.....	55
4.9.6	Get end payload identification status.....	57
4.9.7	Get end payload identification result .....	57
4.9.8	Set sensor end load .....	57
4.9.9	Get sensor end load.....	57
4.9.10	Force-control admittance enable control .....	58
4.9.11	Set the force control type and sensor initial state .....	58
4.9.12	Get the force control type and sensor initial state.....	59
4.9.13	Get the force-control compliance control parameters.....	59
4.9.14	Set the F/T sensor IP address.....	60
4.9.15	Get the F/T sensor IP address .....	60
4.9.16	Disable the torque control.....	60
4.9.17	Set speed compliance control parameters.....	60
4.9.18	Set the compliance control torque conditions.....	61
4.9.19	Set the low-pass filter parameters of the force control .....	61
4.9.20	Get the low-pass filter parameters of the force control.....	61
4.9.21	Set the sensor limit parameter configuration of the sensor.....	61
4.9.22	Get the sensor limit parameter configuration of the sensor .....	62
4.9.23	Zero calibration of sensor.....	62
4.9.24	Get tool drive state.....	62
4.9.25	Get the force sensor's coordinate system in drag mode.....	62
4.9.26	Set the force sensor's coordinate system in drag mode .....	62
4.9.27	Get fusion drive sensitivity.....	63
4.9.28	Set fusion drive sensitivity .....	63
4.9.29	Get motion limit (singularity and joint limit) warning range .....	63
4.9.30	Set motion limit (singularity and joint limit) warning range .....	63
4.9.31	Get compliant speed limit.....	63
4.9.32	Set compliant speed limit .....	63
4.9.33	Get torque reference center.....	64
4.9.34	Set torque reference center .....	64
4.9.35	Get end sensor sensitivity.....	64
4.9.36	Set end sensor sensitivity .....	64
<b>4.10</b>	<b>FTP Services.....</b>	<b>64</b>
4.10.1	Initialize FTP .....	65
4.10.2	Close FTP client.....	65
4.10.3	Interrogate the directory of controller FTP .....	65
4.10.4	Download FTP file.....	65
4.10.5	Upload files to FTP.....	66
4.10.6	Rename FTP files.....	66
4.10.7	Delete FTP files .....	67
<b>5</b>	<b>Feedback and Errata.....</b>	<b>67</b>





## 1 Introduction

This document is a python version of the Software Development Kit document.

## 2 Document Notes

- Running environment: linux python 3.5 32 bits, windows Python 3.7 64 bits
- Units used to parameters: mm, rad.
- In non-specific code examples, the robot is turned on by default and powered on
- All code samples in the documentation default to no interference in the robot's workspace
- The examples in the documentation are all default to the user's Python interpreter being able to find the jkrc module

### 2.1 Use under Linux

Linux needs to libjakaAPI.so and jkrc.so under the same folder and add the current folder path to the environment variable, export LD\_LIBRARY\_PATH=/xx/xx/

### 2.2 Use under Windows

Windows needs to put jkrc and jakaAPI.dll folder, and FAQs can be queried for frequently asked questions.

### 2.3 Dynamic library version number interrogate method

The normal use of jkrc requires a dynamic library file, and here's how to Interrogate the dynamic library version number:

Right-click the dll file in Windows, select the properties, and you can see the version information in the Details tab.

Enter the command strings in **Linux libjakaAPI.so | Grep jakaAPI\_version**

## 3 Data Types

### 3.1 IO type

JAKA robots have three types of IO, which are control cabinet IO, tool IO, and extended IO, respectively.

The following IO definitions are used in the following sample code:

```
IO_CABINET          # Control cabinet IO
IO_TOOL              # tool IO
IO_EXTEND            # extened IO
IO_REALY             # relay IO, DO is only supported on CAB V3 for now
IO_MOUDBUS_SLAVE     # Modbus slave IO, index from 0
IO_PROFINET_SLAVE    # Profinet slave IO, index from 0
IO_EIP_SLAVE         # Ethernet/IP slave IO, index from 0
```

### 3.2 Coordinate system type

JAKA robot has three coordinate systems, namely the base coordinate system / the current user coordinate system, joint space, and the tool coordinate system, respectively. The following coordinate system definitions are used in the following sample code:

```
COORD_BASE = 0      # the base coordinate system / the current user coordinate system
COORD_JOINT = 1      # joint space
COORD_TOOL = 2       # the tool coordinate system
```

### 3.3 Sport type

There are two types of JAKA robot motion, which are defined as follows:

```
ABS = 0              # Absolute move
INCR = 1              # Incremental move
CONTINUE = 2         # Continuous move
```

### 3.4 The return value values

Type	The return value	Describe
<b>ERR_SUCC</b>	0	Success

<b>ERR_INVALID_HANDLER</b>	-1	An invalid handle
<b>ERR_INVALID_PARAMETER</b>	-2	An invalid argument
<b>ERR_COMMUNICATION_ERR</b>	-3	There was a communication error
<b>ERR_KINE_INVERSE_ERR</b>	-4	The reverse solution failed
<b>ERR_EMERGENCY_PRESSED</b>	-5	The emergency stop key has not been released
<b>ERR_NOT_POWERED</b>	-6	The robot is not powered on
<b>ERR_NOT_ENABLED</b>	-7	The robot is not enabled
<b>ERR_DISABLE_SERVOMODE</b>	-8	SERVOMODE mode is not entered
<b>ERR_NOT_OFF_ENABLE</b>	-9	The power is not lowered before power is turned off
<b>ERR_PROGRAM_IS_RUNNING</b>	-10	The program is running
<b>ERR_CANNOT_OPEN_FILE</b>	-11	Opening the file failed
<b>ERR_MOTION_ABNORMAL</b>	-12	Abnormalities during the running process
<b>ERR_FTP_PREFROM</b>	-14	Abnormal FTP
<b>ERR_VALUE_OVERSIZE</b>	-15	Insufficient reserved memory
<b>ERR_KINE_FORWARD</b>	-16	Kine_forward error
<b>ERR_EMPTY_FOLDER</b>	-17	Not support empty folder
<b>ERR_PROTECTIVE_STOP</b>	-20	Protective stop
<b>ERR_EMERGENCY_STOP</b>	-21	Protective stop
<b>ERR_SOFT_LIMIT</b>	-22	On soft limit
<b>ERR_CMD_ENCODE</b>	-30	Fail to encode cmd string
<b>ERR_CMD_DECODE</b>	-31	Fail to decode cmd string
<b>ERR_UNCOMPRESS</b>	-32	Fail to uncompress port 10004 string
<b>ERR_MOVE_L</b>	-40	Move linear error
<b>ERR_MOVE_J</b>	-41	Move joint error
<b>ERR_MOVE_C</b>	-42	Move circular error
<b>ERR_MOTION_TIMEOUT</b>	-50	Block_wait timeout
<b>ERR_POWERON_TIMEOUT</b>	-51	Power on timeout
<b>ERR_POWEROFF_TIMEOUT</b>	-52	Power off timeout
<b>ERR_ENABLE_TIMEOUT</b>	-53	Enable timeoff
<b>ERR_DISABLE_TIMEOUT</b>	-54	Disable timeout
<b>ERR_USERFRAME_SET_TIMEOUT</b>	-55	Set userframe timeout
<b>ERR_TOOL_SET_TIMEOUT</b>	-56	Set tool timeout
<b>ERR_IO_SET_TIMEOUT</b>	-60	Set io timeout

All The return value values of functions are a tuple except the function RC(ip)(as seen in 5.1 Instantiated robots). The return values of the Get class's functions are in the form of (**errcode, data**), the first element is the error code. When the robot is working well, the errcode is equal to 0. Otherwise, the errcode value is not equal to 0, and the value can be queried in the table above. The second element is data, such as joint angle values, and so on.

For example, the function ‘**get\_joint\_position()**’ is utilized to get the joint angles. The return value is (0, [1 2 3 4 5 6]), which means that the joint angles is successfully obtained.

The return value is (-3,0), which indicates the joint angles cannot be obtained due to communication errors.

## 4 Interface

### 4.1 Basic Operation of Robots

#### 4.1.1 Instantiated robots

Function	RC(ip)
Describe	Instantize a robot object
Parameters	ip: The robot's IP address needs to be filled in with a string only the correct IP address instantiated object to control the robot.
The return value	Success: Return a robot object Failed: The created object is destroyed

Sample Code:

```
import jkrc
robot = jkrc.RC("192.168.2.64") # Instantizing a robot object
```

#### 4.1.2 Login

Function	login()
Describe	Connect the robot controller
Parameters	
The return value	Success: (0,) Failed: Others

#### 4.1.3 Logout

Function	logout()
Describe	Disconnect the controller
Parameters	

The return value	Success :(0,)
	Failed: Others

## Sample Code:

```
import jkrc
robot = jkrc.RC("192.168.2.64") # Instantizing a robot object
robot.login()                  #Connect the robot controller
pass
robot.logout()                 #Disconnect the controller
```

## 4.1.4 Power on

Function	power_on()
Describe	Turning on the robot and powering it on. The robot will have a delay of about 8 seconds
Parameters	
The return value	Success: (0,)
	Failed: Others

## Sample Code:

```
import jkrc
robot = jkrc.RC("192.168.2.64") # Instantizing a robot object
robot.login()                   #Login
robot.power_on()                #Power on
robot.logout()                  #logout
```

## 4.1.5 Power off

Function	power_off()
Describe	Turn off the robot
Parameters	
The return value	Success :(0,)
	Failed: Others

## 4.1.6 Shut down robot controller

Function	shut_down()
Describe	The robot control cabinet shuts down
Parameters	
The return value	Success :(0,)
	Failed: Others

## 4.1.7 Enable the robot

Function	enable_robot()
Describe	Enable the robot
Parameters	
The return value	Success :(0,) Failed: Others

### Sample Code:

```
import jkrc
robot = jkrc.RC("192.168.2.64") #Return a robot object
robot.login() #Login
robot.enable_robot() #
robot.logout() #Logout
```

## 4.1.8 Disable the robot

Function	disable_robot()
Describe	disable the robot
Parameters	
The return value	Success :(0,) Failed: Others

## 4.1.9 Get SDK Version No.

Function	get_sdk_version()
Describe	Get the SDK version number
Parameters	
The return value	Success: (0,version) Failed: Others

### Sample Code:

''' Get SDK Version No.'''

```
import jkrc
robot = jkrc.RC("192.168.2.64")#
robot.login() #
ret = robot.get_sdk_version()
print("SDK version is:",ret[1])
```

robot.logout()    #Logout

## 4.1.10 Get the controller IP

Function	get_controller_ip ()
Describe	Get the controller IP
Parameter	
The return value	Success: (0, ip_list), ip_list: indicates the controller IP list. If the controller name is a specific value, the IP address of the controller corresponding to the controller name is returned. If the controller name is empty, all the IP address of the controllers in the network segment is returned Failure: Others

## 4.1.11 Enable drag mode

Function	drag_mode_enable(enable)
Description	Enable drag mode
Parameter	enable :TRUE means to enter the drag mode, FALSE means to quit the drag mode
The return value	Success: (0,) failed: other

Sample Code:

```

1. import jkrc
2. import time
3. #Coordiante System
4. COORD_BASE = 0
5. COORD_JOINT = 1
6. COORD_TOOL = 2
7. #motion mode
8. ABS = 0
9. INCR= 1
10. robot = jkrc.RC("192.168.2.160")
11. robot.login()
12. robot.power_on()
13. robot.enable_robot()
14. robot.drag_mode_enable(True)
15. ret = robot.is_in_drag_mode()
16. print(ret)
17. a = input()
18. robot.drag_mode_enable(False)
19. ret = robot.is_in_drag_mode()
20. print(ret)
21. robot.logout()

```

## 4.1.12 Interrogate whether in drag mode

<b>Function</b>	<b>is_in_drag_mode()</b>
<b>Description</b>	Interrogate whether in drag mode
<b>Parameter</b>	
<b>The return value</b>	Success: (0, state) state is equal to 1: the robot is in drag mode. state is equal to 0: the robot is not in drag mode. Failed: Others

## 4.1.13 Set whether open SDK debug mode

<b>Function</b>	<b>set_debug_mode(mode)</b>
<b>Description</b>	Set whether the SDK enables debug mode.
<b>Parameters</b>	mode: Select TRUE to enter the debug mode. At this time, debugging information will be output in the standard output stream. When selecting FALSE,
<b>Return value</b>	Success: (0,) Failed: Others

## 4.1.14 Set SDK file path

<b>Function</b>	<b>set_SDK_filepath(filepath)</b>
<b>Description</b>	Set SDK file path
<b>Parameters</b>	filepath: File path
<b>Return value</b>	Success: (0,) Failed: Others

## 4.2 Rove Move

Planned motion with controller participation

### 4.2.1 Control robot movement in manual mode

<b>Function</b>	<b>Jog (aj_num , move_mode, coord_type, jog_vel, pos_cmd)</b>
<b>Describe</b>	Control robot movement in manual mode



<b>Parameters</b>	<p>aj_num: Represent joint number [0-5] in joint space, and x, y, z, rx, ry, rz-axis in Cartesian space</p> <p>move_mode: Robot move mode, incremental move(0) or absolute move(1) 2 means continuous move</p> <p>coord_type: Robot move coordinate frame, tool coordinate frame, base coordinate frame (current world/user coordinate frame) or joint space</p> <p>jog_vel: Command velocity, unit of rotation axis or joint move is deg/s, move axis unit is mm/s</p> <p>pos_cmd: Command position, unit of rotation axis or joint move is rad, move axis unit is mm</p>
<b>The return value</b>	<p>Success :(0,)</p> <p>Failed: Others</p>

## Sample Code:

"""jog motion"""

"""1.joint space jog"""

```

1.  # -*- coding: utf-8 -*-
2.  import sys
3.  sys.path.append('D:\\vs2019ws\\PythonCtt\\PythonCtt')
4.  import time
5.  import jkrc
6.  PI=3.1415926
7.  #coordinate
8.  COORD_BASE = 0
9.  COORD_JOINT = 1
10. COORD_TOOL = 2
11. #motion mode
12. ABS = 0
13. INCR= 1
14. #joint1-6,is correspond to 0-5 subscript
15.
16. robot = jkrc.RC("192.168.2.194")#return robot
17. robot.login()#login
18. robot.power_on() #power on
19. robot.enable_robot()
20. print("move1")
21. robot.jog(0,INCR,COORD_JOINT,30*PI/180,PI/2)
22. time.sleep(5)#jog is non-blocking instruction, and if jog instruction received in motion state will be discarded
23. print("move2")
24. robot.jog(0,INCR,COORD_JOINT,5,-90)
25. time.sleep(3)
26. robot.jog_stop()
27. robot.logout()

```

"""2.Cartesian space jog"""

```

1. import jkrc
2. import time
3. COORD_BASE = 0 # base coordinate
4. COORD_JOINT = 1 # joint
5. COORD_TOOL = 2 #tool coordinate
6. ABS = 0 # absolute motion
7. INCR = 1 # incremental motion
8. cart_x = 0 #x direction
9. cart_y = 1 #y direction
10. cart_z = 2 #z direction
11. cart_rx = 3 #rx direction
12. cart_ry = 4 #ry direction
13. cart_rz = 5 #rz direction
14. robot = jkrc.RC("192.168.2.64")#return a robot object
15. robot.login() #login
16. robot.jog(aj_num = cart_z ,move_mode = INCR,coord_type = COORD_BASE ,jog_vel = 5,pos_cmd = 10) # move 10mm in z+
    direction
17. robot.jog_stop()
18. robot.logout() #exit

```

Instruction:

If the robot is approaching a singular posture or joint limit, it will not be able to jog the robot using the above example code

## 4.2.2 Control robot movement stop in manual mode

Function	jog_stop(joint_num)
Describe	Stop the robot in manual mode
Parameters	joint_num: Robot axis number 0-5, when number is -1, stop all axes
The return value	Success :(0,) Failed: Others

Sample Code:

```

1. # -*- coding: utf-8 -*-
2. import sys
3. sys.path.append('D:\\vs2019ws\\PythonCtt\\PythonCtt')
4. import time
5. import jkrc
6. PI=3.1415926
7. #coordinate
8. COORD_BASE = 0
9. COORD_JOINT = 1
10. COORD_TOOL = 2
11. #motion mode

```

```

12. ABS = 0
13. INCR= 1
14. # Joints 1~6 correspond to 0~5 in order,
15.
16. robot = jkrc.RC("192.168.2.160")#return a robot object
17. robot.login()#login
18. robot.power_on() #Power on
19. robot.enable_robot()
20. print("move1")
21. robot.jog(0,INCR,COORD_JOINT,30*PI/180,PI/2)
22. time.sleep(5)# jog is a non-blocking instruction, receiving jog instruction in motion state will be discarded
23. print("move2")
24. robot.jog(0,INCR,COORD_JOINT,5,-PI/2)
25. time.sleep(0.5)
26. robot.jog_stop(0) # Stop after 0.5 seconds of movement, compared with the previous example code
27. robot.logout()

```

## 4.2.3 Robot joint motion

Function	joint_move(joint_pos, move_mode ,is_block, speed)
Description	Robot joint move
Parameter	<p>joint_pos: Joint move position</p> <p>move_mode: 0 for absolute move, 1 for incremental move</p> <p>is_block: Set whether the interface is a block interface, TRUE represents a block interface and FALSE represents a non-block interface. Block means there will be no return value until robot completes its move, while non-block means there will be immediately a return value after the interface call is completed.</p> <p>speed: Robot joint move speed, unit: rad/s</p>
The return value	<p>Success: (0,)</p> <p>Failed: Others</p>

### Sample Code:

"""joint motion"""

```

1. # -*- coding: utf-8 -*-
2. # import sys
3. # sys.path.append('D:\\vs2019ws\\PythonCtt\\PythonCtt')
4. import time
5. import jkrc
6. PI=3.1415926
7. #motion mode
8. ABS = 0
9. INCR= 1
10. joint_pos=[PI/2,PI/3,0,PI/4,0,0]
11. robot = jkrc.RC("192.168.2.160")#return a robot object

```

```

12. robot.login()#login
13. robot.power_on() #上电
14. robot.enable_robot()
15. print("move1")
16. robot.joint_move(joint_pos,ABS,True,1)
17. time.sleep(3)
18. robot.logout()

```

## 4.2.4 Robot extension joint move

Function	joint_move_extend(joint_pos, move_mode, is_block, speed, acc, tol)
Description	Robot extension joint move. Add joint move angular acceleration and endpoint error.
Parameters	<p>joint_pos: Angle of each target joint of robot joint move.</p> <p>move_mode: Specified move mode, 0 for absolute movement, 1 for incremental move, 2 for continuous move</p> <p>is_block: whether a block interface, True means block interface, False means non-block interface.</p> <p>speed: Robot joint move speed, unit: deg/s</p> <p>acc: Robot joint move angular acceleration.</p> <p>tol: Robot joint move endpoint error.</p>
Return value	<p>success: (0, )</p> <p>Failed: other</p>

### Sample Code:

```

1. import jkrc #import module
2. robot = jkrc.RC("192.168.2.226") #returns a robot object
3. robot.login()
4. robot.joint_move_extend(joint_pos=[1, 1, 1, 1, 1, 1],move_mode=0, is_block=True,speed=20,acc=5, tol=0.1)
5. robot.joint_move_extend(joint_pos=[-1, 1, 1, 1, 1, 0],move_mode=0,is_block=true,speed=20,acc=5, tol=0.1)
6. robot.logout() #exit

```

## 4.2.5 Robot end linear move

Function	linear_move(end_pos, move_mode, is_block ,speed)
Description	Robot end linear move
Parameter	<p>end_pos: Robot end move target position</p> <p>move_mode: 0for absolute move, 1for incremental move</p> <p>is_block: Set whether the interface is a block interface, TRUE represents a block interface and FALSE represents a non-block interface.Block means there will be no return value until robot completes its move, while non-block means there will be immediately a return value after the interface call is completed.</p> <p>speed: Robot linear move speed, unit: mm/s</p>
Return value	<p>Success: (0,)</p> <p>Failed: Others</p>

## Sample Code:

"linear motion"

```
1. import time
2. import jkrc
3. PI=3.1415926
4. #motion mode
5. ABS = 0
6. INCR= 1
7. tcp_pos=[0,0,-30,0,0,0]
8. robot = jkrc.RC("192.168.2.160")#return a robot object
9. robot.login()#login
10. robot.power_on() #Power on
11. robot.enable_robot()
12. print("move1")
13. # Blocking 30mm movement at 10mm/s in the negative direction of z-axis
14. ret=robot.linear_move(tcp_pos,INCR,True,10)
15. print(ret[0])
16. time.sleep(3)
17. robot.logout()
```

Note: Due to the difference on robot models, the calculation of kine inverse of the pose value filled in the example above could fail, thus Return value being -4.

## 4.2.6 Robot extension end linear move

Function	<b>linear_move_extend(end_pos, move_mode, is_block, speed, acc, tol)</b>
Description	Robot extension end linear move. Add space acceleration and space motion endpoint error
Parameters	<p>end_pos: Robot end move target position.</p> <p>move_mode:Specify the movement mode,0 is absolute movement,1 is incremental movement</p> <p>is_block: whether a block interface, True means block interface, False means non-block interface.</p> <p>speed: Robot Cartesian space motion speed, unit: mm/s</p> <p>acc: Robot Cartesian space move acceleration, unit: mm/s^2.</p> <p>tol: Robot joint move endpoint error.</p>
Return value	<p>Success: (0,)</p> <p>Failed: Others</p>

## 4.2.7 Arc movement at the robot end

Function	<b>circular_move (end_pos, mid_pos, move_mode, is_block, speed, acc, tol)</b>
Description	Arc movement at the robot end
Parameters	<p>end_pos: Robot end move target position.</p> <p>mid_pos: Middle point of robot end move</p> <p>move_mode: Specified move mode, 0 for absolute movement, 1 for incremental move, 2 for continuous move</p> <p>is_block: whether a block interface, True means block interface, False means non-block interface.</p>

	speed: Robot joint move speed, unit: mm/s acc: Robot joint move angular acceleration. tol: Robot joint move endpoint error.
<b>Return value</b>	Success: (0,) Failed: Others

## Sample Code:

```

1. import jkrc                #import module
2. robot = jkrc.RC("192.168.2.226") #returns a robot object
3. robot.login()
4. robot.circular_move(end_pos = [100, 100, 0, 0, 1, 1],mid_pos = [100, 0, 0, 0, 1, 0],move_mode= 0, is_block = True, speed = 20, a
   cc = 5, tol = 0.1)
5. robot.logout() #exit

```

<b>Function</b>	<b>circular_move_extend (end_pos, mid_pos, move_mode, is_block, speed, acc, tol, cricle_cnt, opt_cond)</b>
<b>Description</b>	Arc movement at the robot end
<b>Parameters</b>	end_pos: Arc move at the end of the robot. mid_pos: The middle point of robot end move. move_mode: Specify move mode, 0 is absolute move, 1 is incremental move, 2 is continuous move. is_block: Set whether the interface is a block interface, TRUE represents a block interface and FALSE represents a non-block interface. speed: Speed of robot MoveL(unit: mm/s) acc: Angular acceleration of robot MoveL(unit: mm/s <sup>2</sup> ) tol: Robot motion endpoint error. circle_cnt: Circle number of MoveC opt_cond: Placeholder, enter none
<b>Return value</b>	Success: (0,) Failed: Others

## Sample Code:

```

1. import jkrc
2. import math
3. import traceback
4.
5.
6. _ABS = 0
7. _BLOCK = 1
8.
9.
10. try:
11.     rc = jkrc.RC("192.168.20.139")
12.     rc.login()
13.     rc.power_on()
14.     rc.enable_robot()
15.
16.     start_pos = [-406.250, 116.250, 374.000, math.pi, 0, math.pi * 0.5]

```

```

17. mid_pos = [-468.650, 211.450, 374.000, math.pi, 0, math.pi * 0.5]
18. end_pos = [-295.050, 267.450, 374.000, math.pi, 0, math.pi * 0.5]
19.
20. rc.joint_move([0] + [math.pi * 0.5] * 3 + [math.pi * -0.5, 0], 0, 1, 200)
21. rc.linear_move(start_pos, _ABS, _BLOCK, 50)
22. rc.circular_move_extend(end_pos, mid_pos, _ABS, _BLOCK, 250, 1200, 5, None, 5)
23. except Exception:
24.     traceback.print_exc()

```

## 4.2.8 Motion abort

Function	<b>motion_abort ()</b>
Description	Ability to terminate the robot's motion in any situation
Parameters	
Return value	Success: (0,) Failed: Others

### Sample Code:

```

1. # -*- coding: utf-8 -*-
2. import sys
3. #sys.path.append('D:\\vs2019ws\\PythonCtt\\lib')
4. import time
5. import jkrc
6. robot = jkrc.RC("192.168.2.160")#Return a robot object
7. robot.login()#login
8. robot.power_on() #power on
9. robot.enable_robot()
10. print("move1")
11. robot.joint_move(joint_pos=[1,0,0,0,0],move_mode=1,is_block=False,speed=0.05)# Incremental motion
12. print("wait")
13. time.sleep(2)
14. print("stop")
15. robot.motion_abort()
16. robot.logout()#exit

```

## 4.2.9 Interrogate whether in position

Function	<b>is_in_pos()</b>
Description	Interrogate whether in position
Parameter	

<b>Return value</b>	<p>Success: (0, state).</p> <p>state is equal to 1: The robot reaches the specified location</p> <p>state is equal to 0: The robot has not reached the specified location.</p> <p>Failed: Others</p>
---------------------	--

## 4.3 Set and Interrogate Robot Operation Info

### 4.3.1 Get robot status (simple)

<b>Function</b>	<b>Get_robot_status_simple()</b>
<b>Description</b>	Get the robot status
<b>Parameter</b>	
<b>The return value</b>	<p>Success: (0, data)</p> <p>Errcode: error code</p> <p>Errmsg: error message</p> <p>Powered_on: whether the robot is powered on</p> <p>Enabled: whether the robot is enabled</p> <p>Failed: Others</p>

### 4.3.2 Get robot status monitor data

<b>Function</b>	<b>get_robot_status ()</b>
<b>Description</b>	Get robot status data monitor data
<b>Parameters</b>	
<b>Return value</b>	<p>success: (0, robotstatus), where the length of robotstatus data is 24, and the data are returned in an order as shown below:</p> <ol style="list-style-type: none"> <li>1. errcode: the error code in case of a robot error, with 0 representing normal operation, and others representing abnormal operation</li> <li>2. inpos: whether the robot is in position, 0 means robot still not move to position, 1 means robot has been moved to position</li> <li>3. power_on: whether the robot is powered on, 0 means not powered on, 1 means powered on</li> <li>4. enabled: whether the robot is enabled, 0 means not enabled, 1 means enabled</li> <li>5. rapidrate: robot speed rate</li> <li>6. protective_stop: whether the robot detects a collision, 0 means no collision detected, 1 means the opposite</li> <li>7. drag_status: whether the robot is in drag status, 0 means not in drag status, 1 means the opposite</li> <li>8. on_soft_limit: whether the robot is on limit, 0 means not triggered limit protection, 1 means triggered limit protection</li> <li>9. current_user_id: the current user coordinate frame ID used by the robot</li> <li>10. current_tool_ID: the current tool coordinate frame ID used by the robot</li> <li>11. dout: robot control cabinet digital output signal</li> <li>12. din: robot control cabinet digital input signal</li> </ol>



	<p>13. aout: robot control cabinet analog output signal</p> <p>14. ain: robot control cabinet analog input signal</p> <p>15. tio_dout: robot end tool digital output signal</p> <p>16. tio_din: robot end tool digital input signal</p> <p>17. tio_ain: robot end tool analog input signal</p> <p>18. extio: robot external extension IO module signal</p> <p>19. cart_position: robot end Cartesian space position value</p> <p>20. joint_position: robot joint space position</p> <p>21. robot_monitor_data: robot status monitor data (scb major version, scb minor version, controller temperature, robot average voltage, robot average current, monitor data of 6 robot joints (transient current, voltage and temperature))</p> <p>22. torq_sensor_monitor_data: robot torque sensor status monitor data (torque sensor IP addresses and port numbers, tool payload (payload mass, centroid x-axis, y-axis and z-axis coordinates), torque sensor status and exception error code, actual contact force values of 6 torque sensors and original reading values of 6 torque sensors)</p> <p>23. is_socket_connect: whether the connection channel of SDK and controller is normal, 0 means abnormal connection channel, 1 means normal connection channel</p> <p>24. emergency_stop      whether the robot is emergency stopped, 0 means not pressed the emergency-stop button, 1 means the opposite</p> <p>25. tio_key      Robot end tool button [0] free; [1] point; [2] end light button</p> <p>Failed: Others</p> <p><b>Notes:</b>  <b>If the robot has no corresponding IO, it will return such a string as "no extio".</b>  The error code file can be found in the <b>JAKA secondary development kit \ reference material</b></p>
--	---

#### Sample Code:

```

1. import sys
2. import jkrc
3. import time
4.
5. robot = jkrc.RC("192.168.2.160")
6. robot.login()
7. ret = robot.get_robot_status()
8. if ret[0] == 0:
9.     print("the joint position is :",ret[1])
10.    print(len(ret[1]))
11.    for i in range(len(ret[1])):
12.        print(ret[1][i])
13. else:
14.    print("some things happend,the errcode is: ",ret[0])
15. robot.logout()

```

### 4.3.3 Set robot status data update time interval

Function	Set_status_data_update_time_interval (millisecond)
Description	Set the robot status data update time interval to change the system occupied storage, the default is to send as quick as possible to ensure the data is the newest (4ms)
Parameter	Millisecond: time parameters, uint: ms.

<b>The return value</b>	Success: (0,)
	Failed: Others

Sample Code:

```

1. import jkrc                #import modules
2. robot = jkrc.RC("192.168.2.165") #return to a robot
3. robot.login()
4. robot.set_status_data_update_time_interval(100)
5. robot.logout()

```

## 4.3.4 Get joint angles

<b>Function</b>	<b>get_joint_position()</b>
<b>Description</b>	Get the robot 6 joint values
<b>Parameter</b>	
<b>The return value</b>	Success: joint_pos is a tuple with 6 elements (j1, j2, j3, j4, j5, j6), J1, J2, J3, J4, J5, and j6 represent the Angle values from joint 1 to joint 6 respectively Failed: Others

Sample Code:

"""get joints degrees"""

```

1. # -*- coding: utf-8 -*-
2. import sys
3. #sys.path.append('D:\\vs2019ws\\PythonCtt\\lib')
4. import time
5. import jkrc
6. PI=3.1415926
7. robot = jkrc.RC("192.168.2.160")#returns a robot object
8. ret = robot.login()#login
9. ret = robot.get_joint_position()
10. if ret[0] == 0:
11.     print("the joint position is :",ret[1])
12. else:
13.     print("some things happend,the errcode is :",ret[0])
14. robot.logout() #exit

```

## 4.3.5 Get TCP pose

<b>Function</b>	<b>get_tcp_position()</b>
<b>Description</b>	Get tcp pose
<b>Parameter</b>	

<b>Return value</b>	Success: (0, Cartesian_pose), where Cartesian_pose is a tuple containing 6 elements (x,y,z,rx,ry,rz), with x,y,z,rx,ry,rz representing the pose value of robot tool end Failed: Others
---------------------	---

Sample Code:

```
''' Get TCP pose '''
1. # -*- coding: utf-8 -*-
2. import sys
3. #sys.path.append('D:\\vs2019ws\\PythonCtt\\lib')
4. import time
5. import jkrc
6. PI=3.1415926
7. robot = jkrc.RC("192.168.2.160")#returns a robot object
8. ret = robot.login()#login
9. ret = robot.get_tcp_position()
10. if ret[0] == 0:
11.     print("the tcp position is :",ret[1])
12. else:
13.     print("some things happend,the errcode is :",ret[0])
14. robot.logout() #exit
```

## 4.3.6 Set user coordinate frame parameter

<b>Function</b>	<b>set_user_frame_data(id, user_frame, name)</b>
<b>Description</b>	Set the parameter of specified user coordinate frame
<b>Parameter</b>	id :The value range of the user coordinate frame number is [1,10], 0 for robot-based coordinate frame user_frame: Offset value of user coordinate frame[x,y,z,rx,ry,rz]
<b>Return value</b>	Success: (0,) Failed: Others

## 4.3.7 Get user coordinate frame data

<b>Function</b>	<b>get_user_frame_data()</b>
<b>Description</b>	Get user coordinate frame ID
<b>Parameters</b>	
<b>Return value</b>	Success: (0, id, tcp) id The value range of the user coordinate frame number is [1,10], where 0 represents robot basic coordinate frame tcp: Offset value of user coordinate frame[x,y,z,rx,ry,rz] Failed: Others

## 4.3.8 Get user coordinate frame ID

<b>Function</b>	<b>get_user_frame_id(id)</b>
-----------------	------------------------------

<b>Description</b>	Get user coordinate frame ID
<b>Parameter</b>	
<b>Return value</b>	Success: (0, id) The value range of the id is [0,10], where 0 represents the world coordinate frame Failed: Others

## 4.3.9 Set user coordinate frame ID

<b>Function</b>	<b>set_user_frame_id(id)</b>
<b>Description</b>	Set user coordinate frame ID
<b>Parameter</b>	id: The value range of the user coordinate frame ID is [0,10], where 0 represents the world coordinate frame
<b>Return value</b>	Success: (0,) Failed: Others

## 4.3.10 Set the tool information for the specified number

<b>Function</b>	<b>set_tool_data(id, tcp, name)</b>
<b>Description</b>	Set the tool information for the specified number
<b>Parameters</b>	id : Set the tool ID, optional ID is 1 to 10, 0 means end flange, already used by controller. tcp : Set tool coordinate system parameters [x,y,z,rx,ry,rz]. name: alias of user coordinate system
<b>Return values</b>	Success: (0,) Failed: Others

## 4.3.11 Set tool ID

<b>Function</b>	<b>set_tool_id(id)</b>
<b>Description</b>	Set tool ID
<b>Parameter</b>	Id:The value range of tool coordinate frame ID is [0,10], 0 means no tools, flange center
<b>Return value</b>	Success: (0,) Failed: Others

## 4.3.12 Interrogate target tool coordinate frame ID

<b>Function</b>	<b>get_tool_data(id)</b>
<b>Description</b>	Interrogate the tool ID used by robot
<b>Parameters</b>	
<b>Return value</b>	Success: (0,(id,tcp)), where the ID values range from 0 to 10, with 0 representing the end flange, which has been used by controller.

	tcp: tool coordinate frame parameter [x,y,z,rx,ry,rz] Failed: Others
--	---

## 4.3.13 Get the tool ID currently in use

Function	get_tool_id()
Description	Get the tool ID currently in use
Parameter	
Return value	Success: (0, id), where the ID values range from 0 to 10, with 0 representing the end flange, which has been used by controller. Failed: Others

### Sample Code:

```

1.  # -*- coding: utf-8 -*-
2.  import sys
3.  sys.path.append('D:\\vs2019ws\\PythonCtt\\PythonCtt')
4.  import time
5.  import jkrc
6.  PI=3.1415926
7.
8.  robot = jkrc.RC("192.168.2.160") #returns a robot object
9.  robot.login()                  #login
10. ret = robot.get_tool_data(1)   #Get tool coordinate system data
11. if ret[0] == 0:
12.     print("the tool data is :",ret)
13. else:
14.     print("some things happend,the errcode is: ",ret[0])
15. robot.set_tool_data(1,[0,0,1,0,0,0],'testlx') # Set tool coordinate system data
16. time.sleep(0.5)
17. ret = robot.get_tool_data(1)   #Get tool coordinate system data
18. if ret[0] == 0:
19.     print("the tool data is :",ret)
20. else:
21.     print("some things happend,the errcode is: ",ret[0])
22. ret = robot.get_tool_id()      #Get tool coordinate system id
23. print("tool_id",ret)
24. robot.set_tool_id(1)          #Set tool coordinate system data
25. time.sleep(0.5)
26. ret = robot.get_tool_id()      # Get tool coordinate system id
27. print("tool_id",ret)
28. robot.logout()

```

## 4.3.14 Set digital output variables

Function	set_digital_output(iotype = a_type, index = a_number, value = a_value)
Description	Set DO Value

<b>Parameter</b>	Iotype: DO Type Index: DO Index Value: DO Value
<b>Return value</b>	Success: (0,) Fail: other

Sample Code:

""" Set the value of DO3 to 1 """

```

1. # -*- coding: utf-8 -*-
2. import sys
3. sys.path.append('D:\\vs2019ws\\PythonCtt\\PythonCtt')
4. import time
5. import jkrc
6. PI=3.1415926
7.
8. IO_CABINET = 0 #controller panel IO
9. IO_TOOL = 1 #Tool IO
10. IO_EXTEND = 2 #extension IO
11.
12. robot = jkrc.RC("192.168.2.160")
13. robot.login()
14. ret = robot.get_digital_output(0,2)
15. if ret[0] == 0:
16.     print("1the DO2 is :",ret[1])
17. else:
18.     print("some things happend,the errcode is :",ret[0])
19. robot.set_digital_output(IO_CABINET, 2, 1)# Set the pin output value of DO2 to 1
20. time.sleep(0.1)
21. ret = robot.get_digital_output(0, 2)
22. if ret[0] == 0:
23.     print("2the DO2 is :",ret[1])
24. else:
25.     print("some things happend,the errcode is :",ret[0])
26. robot.logout() #exit

```

## 4.3.15 Set analog output variables

<b>Function</b>	<b>set_analog_output(iotype = a_type, index = a_number, value = a_value)</b>
<b>Description</b>	Set analog output (AO) value
<b>Parameter</b>	Iotype: AO Type Index: AO Index Value: AO Settings
<b>Return value</b>	Success: (0,) Failed: Others

Sample Code:

"""Set the value of AO4 to 1.55"""

```

1. Example:
2. ''' Set the value of AO4 to 1.55'''
3. import jkrc
4. IO_CABINET = 0 #controller panel IO
5. IO_TOOL = 1 #Tool IO
6. IO_EXTEND = 2 #extension IO
7. robot = jkrc.RC("192.168.2.64")
8. robot.login()
9. robot.set_analog_output(iotype = IO_CABINET,index = 3,value = 1.55)#
10. robot.logout() #exit

```

## 4.3.16 Get digital input status

Function	get_digital_input(iotype, index)
Description	Interrogate DI status
Parameter	Iotype: DI Type Index: DI Index (starting from 0)
Return value	Success: (0,value), value: Interrogate result of DI status Failed: Others

## 4.3.17 Get digital output status

Function	get_digital_output(iotype, index)
Description	Interrogate DO status
Parameter	Iotype: DO Type Index: DO Index
Return value	Success: (0,value) value:Interrogate result of DO status Failed: Others

## 4.3.18 Get analog input variables

Function	get_analog_input(iotype, index)
Description	Get the type of AI value
Parameter	iotype: AI Type index: AI Index (starting from 0)
Return value	Success: (0,value) result: Interrogate result of AI status (expressed as a floating point), Failed: Others

## 4.3.19 Get analog output variables

<b>Function</b>	<b>get_analog_output(type, index)</b>
<b>Description</b>	Get AO value
<b>Parameter</b>	type: AO Type index: AO Index (starting from 0)
<b>Return value</b>	Success: (0,value) result: Interrogate result of AO status (expressed as a floating point), Failed: Others

### Sample Code:

"Interrogate the value of AO4 to"

```

1. Example:
2. "Interrogate the value of AO4 to "
3. import jkrc
4. IO_CABINET = 0 # controller panel IO
5. IO_TOOL = 1 #Tool IO
6. IO_EXTEND = 2 #Extension IO
7. robot = jkrc.RC("192.168.2.64")
8. robot.login()
9. robot.set_analog_output(iotype = IO_CABINET,index = 3,value = 1.55)
10. ret = robot.get_analog_output(iotype = IO_CABINET,index = 3)
11. print("AO value is:",ret[1])
12. robot.logout() #exit

```

## 4.3.20 Interrogate whether extension IO in running status

<b>Function</b>	<b>is_extio_running()</b>
<b>Description</b>	Interrogate whether the extension IO module is running
<b>Parameter</b>	
<b>Return value</b>	Success: (0,status) That status is 1 means running Failed: Others

## 4.3.21 Set payload

<b>Function</b>	<b>set_payload(mass = m, centroid = [x,y,z])</b>
<b>Description</b>	Set payload
<b>Parameter</b>	mass: payload mass, unit: kg centroid: payload centroid coordinates[x, y, z], unit: mm



<b>Return value</b>	Success: (0) Failed: Others
---------------------	--------------------------------

Example:

```

1. import jkrc                #import module
2. robot = jkrc.RC("192.168.2.226") #returns a robot object
3. robot.login()
4. robot.set_payload(mass= 1, centroid =[0.01,0.02,0.03])
5. robot.logout()            #exit

```

## 4.3.22 Get payload data

<b>Function</b>	get_payload()
<b>Description</b>	Get payload data
<b>Parameter</b>	
<b>Return value</b>	Success: (0 , payload)    The expression of payload is (mass, (x, y, z)). payload is a tuple,whose length is 2.The first element of tuple is the mass of payload.The second element of tuple is the centroid of payload. Failed: Others

```

1. """ Set payloads"""
2. import jkrc
3. robot = jkrc.RC("192.168.2.64") # returns a robot object
4. robot.login()                #exit
5. robot.set_payload(mass= 1,centroid =[0.01,0.02,0.03])
6. ret = robot.get_payload()
7. if ret[0] == 0:
8.     print("the payload is :",ret[1])
9. else:
10.    print("some things happend,the errcode is :",ret[0])
11. robot.logout()

```

## 4.3.23 Set tioV3 parameters

<b>Function</b>	set_tio_vout_param (vout_enable ,vout_vol)
<b>Description</b>	Set tioV3 parameters
<b>Parameters</b>	vout_enable voltage enable, 0:close, 1 open vout_vol voltage volume 0:24v 1:12v
<b>Return value</b>	Success: (0) Failed: Others

## 4.3.24 Get tioV3 parameters

<b>Function</b>	get_tio_vout_param (vout_enable ,vout_vol)
-----------------	--

<b>Description</b>	Get tioV3 parameters
<b>Parameters</b>	vout_enable voltage enable, 0:close, 1 open vout_vol voltage volume 0:24v 1:12v
<b>Return value</b>	Success: (0,(vout_enable ,vout_vol)) Failed: Others

## 4.3.25 Get robot state

<b>Function</b>	<b>get_robot_state()</b>
<b>Description</b>	Get robot state
<b>Parameter</b>	
<b>Return value</b>	Success: (0, state), where state is a tuple containing 3 elements, representing whether emergency stop, whether power on, and whether servo enable, respectively. 1 for yes, 0 for no. Failed: Others

Sample Code:

```

1.  #-*- coding: utf-8 -*-
2.  import sys
3.  #sys.path.append('D:\\vs2019ws\\PythonCtt\\lib')
4.  import time
5.  import jkrc
6.
7.  robot = jkrc.RC("192.168.2.160")#returns a robot object
8.  ret = robot.login()#login
9.
10. ret = robot.get_robot_state()
11. if ret[0] == 0:
12.     print("the robot state is :",ret[1])
13. else:
14.     print("some things happend,the errcode is: ",ret[0])
15. robot.logout() #exit

```

## 4.3.26 TIO add or modify semaphore

<b>Function</b>	<b>add_tio_rs_signal ( sign_info )</b>
<b>Description</b>	Add or modify semaphore
<b>Parameters</b>	sign_info: dict Semaphore attribute
<b>Return value</b>	Success: (0,) Failed: Others

Sample Code:

```

1.  def example_add_tio_rs_signal():
2.      rc = jkrc.RC(_RC_ADDRESS)
3.      rc.login()
4.      ret = rc.add_tio_rs_signal({

```

```

5.         'sig_name': 'signal_tmp', //Signal name
6.         'chn_id': 0, //RS485channel ID
7.         'sig_type': 0, //Semaphore type
8.         'sig_addr': 0x1, //Register address
9.         'value': 5, //Value Invalid when setting
10.        'frequency': 5 // The refresh frequency of semaphore in the controller is not more than 10.
11.    })

```

## 4.3.27 TIO delete semaphore

<b>Function</b>	<code>del_tio_rs_signal ( sign_name )</code>
<b>Description</b>	Add or modify semaphore
<b>Parameters</b>	sign_info: str Semaphore identification name
<b>Return value</b>	Success: (0, Failed: Others

Sample Code:

```

1. def example_del_tio_rs_signal():
2.     rc = jkrc.RC(_RC_ADDRESS)
3.     rc.login()
4.     ret = rc.del_tio_rs_signal('signal_tmp')
5.     print('ret is {}'.format(ret))

```

## 4.3.28 TIO RS485 send command

<b>Function</b>	<code>send_tio_rs_command(chn_id, cmd)</code>
<b>Description</b>	RS485 send command
<b>Parameters</b>	chn_id: int channel number data: str Data bit ; Convert hex string to byte array
<b>Return value</b>	Success: (0, Failed: Others

Sample Code:

```

1. def example_send_tio_rs_command():
2.     rc = jkrc.RC(_RC_ADDRESS)
3.     rc.login()
4.     ret = rc.send_tio_rs_command( 2,
5.     bytearray.fromhex("01 06 01 00 00 01"))
6.     print('ret is {}'.format(ret))

```

## 4.3.29 TIO get semaphore information

<b>Function</b>	get_rs485_signal_info()
<b>Description</b>	RS485 semaphore information
<b>Parameters</b>	
<b>Return value</b>	Success: (0,sign_info_list) sign_info_list: list Semaphore information array Failed: Others

Sample Code:

```

1. def example_get_rs485_signal_info():
2.     rc = jkrc.RC(_RC_ADDRESS)
3.     rc.login()
4.     ret, sign_info_list = rc.get_rs485_signal_info()
5.     print('ret is: { }, sign_info_list: { }'.format(ret, sign_info_list))
6.     # [{'value': 0, 'chn_id': 0, 'sig_addr': 0, 'sig_name': '', 'sig_type': 0, 'frequency'
    0}, ...] -> 4.3.26TIOadd or modify semaphore

```

## 4.3.30 TIO Setting TIO mode

<b>Function</b>	set_tio_pin_mode(pin_type, pin_mode)
<b>Description</b>	Settio mode
<b>Parameters</b>	<p>pin_type: tio type 0 for DI Pins, 1 for DO Pins, 2 for AI Pins</p> <p>pin_mode: tio mode <b>DI Pins:</b></p> <p>0:0x00 DI2 is NPN, DI1 is NPN, 1:0x01 DI2 is NPN, DI1: PNP, 2:0x10 DI2 is PNP, DI1 is NPN, 3:0x11 DI2 is PNP, DI1 is PNP</p> <p><b>DO Pins:</b> The lower 8 bits of data and the upper 4 bits are configured as DO2, The lower four bits are DO1 configuration, 0x0 DO is NPN output, 0x1 DO PNP output, 0x2 DO is push-pull output, 0xF RS485H interface</p> <p><b>AI Pins:</b></p> <p>0: Analog input function is enabled, RS485L is disabled, 1: RS485L interface is enabled and analog input function is disabled.</p>

<b>Return value</b>	Success: (0,) Failed: Others
---------------------	---------------------------------

## 4.3.31 TIO get TIO mode

<b>Function</b>	<b>get_tio_pin_mode(pin_type)</b>
<b>Description</b>	Get tio mode
<b>Parameters</b>	pin_type: tio type 0 for DI Pins, 1 for DO Pins, 2 for AI Pins
<b>Return value</b>	Success: (0, pin_mode) Failed: Others

## 4.3.32 TIO RS485 communication parameter configuration

<b>Function</b>	<b>set_rs485_chn_comm(dict)</b>
<b>Description</b>	Configure RS485 communication parameters
<b>Parameters</b>	When the channel mode is set to Modbus RTU, specify the Modbus slave ID Additionally The parameter type is a dictionary: dict = { 'chn_id':1, 'slave_id':1, 'baudrate': 115200, 'databit': 8, 'stopbit': 1, 'parity': 78 }
<b>Return value</b>	Success: (0, ) Failed: Others

## 4.3.33 TIO RS485 Communication Parameter Query

<b>Function</b>	<b>get_rs485_chn_comm(chn_id, slave_id, baudrate, databit, stopbit, parity)</b>
<b>Description</b>	Query RS485 communication parameters
<b>Parameters</b>	mod_rtu_com When querying, chn_id serves as an input parameter
<b>Return value</b>	Success: (0, (chn_id, slave_id, baudrate, databit, stopbit, parity)) Failed: Others

## 4.3.34 TIO RS485 communication mode configuration

<b>Function</b>	<b>set_rs485_chn_mode(chn_id, chn_mode)</b>
<b>Description</b>	Configure RS485 communication mode
<b>Parameters</b>	chn_id 0: RS485H, channel 1; 1: RS485L, channel 2 chn_mode 0: Modbus RTU, 1: Raw RS485, 2: Torque Sensor
<b>Return value</b>	Success: (0, (chn_id, slave_id, baudrate, databit, stopbit, parity)) Failed: Others

## 4.3.35 TIO RS485 communication mode configuration

<b>Function</b>	<code>get_rs485_chn_mode(chn_id)</code>
<b>Description</b>	Query RS485 communication mode
<b>Parameters</b>	chn_id Input parameter: 0 for RS485H, channel 1; 1 for RS485L, channel 2
<b>Return value</b>	Success: (0, chn_mode) chn_mode 0: Modbus RTU, 1: Raw RS485, 2: Torque Sensor Failed: Others

## 4.3.36 Set robot installation angle

<b>Function</b>	<code>set_installation_angle(anglex, angley)</code>
<b>Description</b>	Set the installation angle
<b>Parameters</b>	anglex: Rotation angle around the X-axis, range: 0-180 deg angley: Rotation angle around the Z-axis, range: 0-360 deg
<b>Return value</b>	Success: (0, ) Failed: Others

### Sample Code:

```

1. import jkrc
2. rc = jkrc.RC("192.168.137.152")
3. res = rc.login()
4. if res[0] != 0:
5.     raise "rc login failed."
6.
7. anglex = 180
8. angley = 0
9. res = rc.set_installation_angle(anglex, angley)
10. if res[0] != 0:
11.     raise "set installation angle failed."
12.
13. res = rc.get_installation_angle()
14. if res[0] != 0:
15.     raise "get installation angle failed."
16.
17. print("installation angle:")
18. print("quat: [{x}, {y}, {z}, {s}]"
        .format(s=res[1][0], x=res[1][1], y=res[1][2], z=res[1][3]))
19. print("rpy: [{rx}, {ry}, {rz}]"
        .format(rx=res[1][4], ry=res[1][5], rz=res[1][6]))
20. rc.logout()
21.

```

## 4.3.37 Get robot installation angle

<b>Function</b>	<code>get_installation_angle()</code>
<b>Description</b>	Get the installation angle of robot
<b>Parameters</b>	
<b>Return value</b>	Success: (0, [qs, qx, qy, qz, rx, ry, rz]) qs, qx, qy, qz: Quaternion representing the installation angle rx, ry, rz: Installation angles in Roll-Pitch-Yaw (RPY) format Failed: Others

## 4.4 Robot Safety Status Settings

### 4.4.1 Interrogate whether on limit

<b>Function</b>	<code>is_on_limit()</code>
<b>Description</b>	Interrogate whether on limit
<b>Parameter</b>	
<b>Return value</b>	Success: (0, state). state is equal to 1: The robot movement is beyond the limited range state is equal to 0: The robot movement is in the limited range Failed: Others

### 4.4.2 Interrogate whether in Collision Protection mode

<b>Function</b>	<code>is_in_collision()</code>
<b>Description</b>	Interrogate whether in Collision Protection mode
<b>Parameter</b>	
<b>Return value</b>	Success: (0, state). state is equal to 1: the Collision Protection mode is active. state is equal to 0: the Collision Protection mode is not active. Failed: Other

### 4.4.3 Clear the robot error code after collision occur

<b>Function</b>	<code>collision_recover()</code>
<b>Description</b>	Clear the robot error code after collision occur
<b>Parameters</b>	
<b>Return value</b>	Success: (0,) Failed: Other

## Sample Cide:

```
1. from typing import Counter
2. import jkrc
3. import time
4.
5.
6. robot = jkrc.RC("192.168.2.160")
7. robot.login()
8. robot.power_on()
9. robot.enable_robot()
10. ret = robot.get_collision_level()#gets the current collision level
11. print(ret)
12. robot.set_collision_level(1)#set collision level
13. ret = robot.get_collision_level()
14. print(ret)
15. num = 0
16. while(1):
17.     ret = robot.is_in_collision() #Interrogate whether in Collision Protection mode
18.     collision_status = ret[1]
19.     if collision_status == 1:
20.         time.sleep(5)
21.         robot.collision_recover() #Clear the robot error code after collision occur
22.         print(" in collision " + str(num))
23.     else:
24.         print("the robot is not in collision " + str(num))
25.     time.sleep(1)
26.     num=num+1
27.
28. robot.logout()
```

## 4.4.4 Set collision level

Function	set_collision_level(level)
Description	Set collision level
Parameter	level: the range of collision value is [0,5], 0: close collision, 1: collision threshold 25N, 2: collision threshold 50N, 3: collision threshold 75N, 4: collision threshold 100N, 5: collision threshold 125N
Return value	Success: (0,) Failed: Others



## 4.4.5 Get collision level

<b>Function</b>	<b>get_collision_level()</b>
<b>Description</b>	get collision level
<b>Parameter</b>	
<b>Return value</b>	Success: (0,level) level: the collision level. 0: close collision, 1: collision threshold 25N, 2: collision threshold 50N, 3: collision threshold 75N, 4: collision threshold 100N, 5: collision threshold 125N

## 4.4.6 Get the last error code

<b>Function</b>	<b>get_last_error ()</b>
<b>Description</b>	Get the last error code in the robot running process, when clear_error is called, the last error code will be cleared. If you need to use the get_last_error interface, set the error code file path. If you just need to get the error code, there is no need to call set_errorcode_file_path.
<b>Parameter</b>	
<b>Return value</b>	Success: (0, error) Failed: Others

### Sample Code:

```

1. import jkrc
2. robot = jkrc.RC("192.168.2.194") #return a robot object
3. robot.login() #login
4. robot.program_load("not_exist") #Intentionally load a non-existent program, causing an error
5. ret = robot.get_last_error () #Without setting the error code file path, you can only get the error code, not the specific error information
6. print(ret[1])
7. robot.set_errorcode_file_path("D:\\JAKA_ERROR_CODE.csv") # The error file path cannot contain Chinese
8. ret = robot.get_last_error () # You can get the error code and specific error information after setting error code file path
9. print(ret[1])
10. robot.logout() #exit

```

## 4.4.7 Set error code file path

Function	set_errcode_file_path (errcode_file_path)
Description	Set the error code file path. If you need to use the get_last_error interface, set the error code file path. If no need to use the get_last_error interface, do not set the interface. <b>Note: The path can not contain any Chinese characters, otherwise it will not work</b>
Parameter	errcode_file_path: The path where the error code file is stored. The error code file can be found in the JAKA secondary development kit\reference material
Return value	Success: (0,) Failed: Others

## 4.4.8 Clear error status

Function	clear_error()
Description	Clear error status.
Parameters	
Return value	Success: (0,) Failed: Others

### Sample Code:

Refer to collision protection mode recovery

## 4.4.9 Set the robot automatic move termination types upon network exceptions

Function	set_network_exception_handle (millisecond, mnt)
Description	Set the network exception control handle to control the robot motion status upon network exceptions.
Parameters	millisecond: The time parameter, unit: ms. mnt: the motion types the robot needs to perform upon network exceptions. 0 means that the robot should keep its current move, 1 means that the robot should pause its move and 2 means the robot should stop its move.
Return value	Success: (0,) Failed: Others

### Sample Code:

```

1. # -*- coding: utf-8 -*-
2. # import sys
3. # sys.path.append('D:\\vs2019ws\\PythonCtt\\PythonCtt')
4. import time
5. import jkrc
6. PI=3.1415926
7. #motion mode
8. ABS = 0

```

```

9. INCR= 1
10. robot = jkrc.RC("192.168.2.160")#return a robot object
11. robot.login()#login
12. robot.power_on() #power on
13. robot.enable_robot()
14. robot.set_network_exception_handle(100,2)#Set 100ms, move abort.
15. print("move1")
16. num=0
17. while(1):
18.     robot.joint_move([1,1,1,1,1,1],ABS,False,0.5)
19.     robot.joint_move([-1,1,1,1,1,1],ABS,False,0.5)
20.     num = num + 1
21.     print(num)
22.     time.sleep(6)
23. robot.logout()

```

## 4.5 Use APP Script Program

### 4.5.1 Load the specified program

<b>Function</b>	<b>program_load(file_name)</b>
<b>Description</b>	Run the loaded program
<b>Parameter</b>	file_name :program name likes “file_name”
<b>Return value</b>	Success: (0,) Failed: Others

### 4.5.2 Get the loaded program

<b>Function</b>	<b>get_loaded_program()</b>
<b>Description</b>	Get the name of the loaded operating program
<b>Parameter</b>	
<b>Return value</b>	Success: (0,file_name) Failed: Others

#### Sample Code:

```

1. import jkrc
2. robot = jkrc.RC("192.168.2.64")#returns a robot object
3. robot.login() #login
4. ret = robot.program_load("program_test")# Load the script program_test written through the app, you need to write it yourself
5. ret = robot.get_loaded_program()
6. print("the loaded program is:",ret[1])
7. robot.logout() #exit

```

## 4.5.3 Get current line

<b>Function</b>	<b>get_current_line()</b>
<b>Description</b>	Get current line
<b>Parameters</b>	
<b>Return value</b>	Success: (0,curr_line),curr_line: Interrogate result of current line number. Failed: Others

## 4.5.4 Run the loaded program

<b>Function</b>	<b>program_run()</b>
<b>Description</b>	Run the loaded program
<b>Parameter</b>	
<b>Return value</b>	Success: (0,) Failed: Others

## 4.5.5 Pause the running program

<b>Function</b>	<b>program_pause()</b>
<b>Description</b>	Pause the running program
<b>Parameter</b>	
<b>Return value</b>	Success: (0,) Failed: Others

## 4.5.6 Resume program

<b>Function</b>	<b>program_resume()</b>
<b>Description</b>	Resume program
<b>Parameter</b>	
<b>Return value</b>	Success: (0,) Failed: Others

## 4.5.7 Abort program

<b>Function</b>	<b>program_abort()</b>
-----------------	------------------------

<b>Description</b>	Abort program
<b>Parameter</b>	
<b>Return value</b>	Success: (0,) Failed: Others

## 4.5.8 Get program status

<b>Function</b>	<b>get_program_state()</b>
<b>Description</b>	Get the program status
<b>Parameter</b>	
<b>Return value</b>	Success: (0, state) That state is equal to 0 stands for stoped. That state is equal to 1 stands for running. That state is equal to 2 stands for paused. Failed: Others

### Sample Code:

```

1.  # -*- coding: utf-8 -*-
2.  import sys
3.  sys.path.append('D:\\vs2019ws\\PythonCtt\\PythonCtt')
4.  import time
5.  import jkrc
6.  import _thread
7.  PI=3.1415926
8.
9.  def print_state(name,robot):
10.     while(1):
11.         ret = robot.get_program_state() # Interrogate the program running status, 0 represents for Program terminated or no program
            running, 1 represents for Program running, 2 represents for Pause
12.         print("the robot program state is:",ret[1])
13.         time.sleep(1)
14.
15. robot = jkrc.RC("192.168.2.160")#returns a robot object
16. robot.login() #login
17. ret = robot.program_load("simple")# Load the script program_test written through the app, you need to write it yourself
18. ret = robot.get_loaded_program()
19. print("the loaded program is:",ret[1])
20. robot.program_run()
21. _thread.start_new_thread( print_state,("p1_state", robot))# Open a "p1" thread to interrogate the program status
22. time.sleep(10)
23. robot.program_pause() #pause
24. time.sleep(10)
25. robot.program_resume() #resume
26. time.sleep(10)
27. robot.program_abort() #abort
28. time.sleep(3)

```

```
29. robot.logout()      #exit
```

## 4.5.9 Set rapid rate

<b>Function</b>	<b>set_rapidrate(rapid_rate)</b>
<b>Description</b>	Set robot rapid rate
<b>Parameter</b>	rapid_rate:Set robot rapid rate
<b>Return value</b>	Success: (0,) Failed: Others

## 4.5.10 Get rapid rate

<b>Function</b>	<b>get_rapidrate()</b>
<b>Description</b>	Get robot rapid rate
<b>Parameter</b>	
<b>Return value</b>	Success: (0, rapidrate) rapidrate is the speed rate, and Returned value is within a closed interval between 0 and 1 Failed: Others

## 4.6 Trajectory Reproduction

### 4.6.1 Set trajectory track configuration parameter

<b>Function</b>	<b>set_traj_config(xyz_interval, rpy_interval, vel, acc)</b>
<b>Description</b>	In setting the trajectory track configuration parameters, you can set the space position sample accuracy, pose sample accuracy, script execution running speed and script execution running acceleration.
<b>Parameters</b>	xyz_interval: Space position acquisition speed rpy_interval: Orientation capture accuracy vel: Script execution running speed acc: Script execution running acceleration
<b>Return value</b>	Success: (0,) Failed: Others

Sample Code:

```
1. import jkrc
2. import time
3.
4. #coordinate system
5. COORD_BASE = 0
6. COORD_JOINT = 1
7. COORD_TOOL = 2
```

```

8. #motion mode
9. ABS = 0
10. INCR= 1
11.
12. robot = jkrc.RC("192.168.2.160")
13. robot.login()
14. robot.power_on()
15. robot.enable_robot()
16. robot.joint_move(joint_pos =[1,1,1,1,1,1] ,move_mode = 0 ,is_block = True ,speed = 10 )
17. print("joint")
18. robot.set_traj_config([0.1, 0.1, 25, 100]) #Set track recurrence parameters, only the recording process is valid
19. time.sleep(0.1)
20. ret = robot.get_traj_config()#get trajectory recurrence parameters
21. print("traj_config:")
22. print(ret)
23. robot.set_traj_sample_mode(True, 'pythonTrack')#enable trajectory recurrence capture
24. time.sleep(0.1)
25. robot.joint_move(joint_pos =[-1,1,1,1,1,1] ,move_mode = 0 ,is_block = True ,speed = 30*3.14/180 )#blocking motion
26. robot.joint_move(joint_pos =[1,1,1,1,1,1] ,move_mode = 0 ,is_block = True ,speed = 30*3.14/180 )
27. # robot.jog(2,INCR,COORD_BASE,10,-2)
28. # robot.jog(2,INCR,COORD_BASE,10,2)
29. robot.set_traj_sample_mode(False, 'pythonTrack')# disable trajectory recurrence capture
30. time.sleep(1)
31. res = robot.generate_traj_exe_file('pythonTrack')# convert the captured trajectory files into scripts
32. print(res)
33. robot.program_load("track/pythonTrack")#loading trajectory programs
34. time.sleep(0.1)
35. robot.program_run()

```

## 4.6.2 Get trajectory track configuration parameters

Function	get_traj_config()
Description	By getting the trajectory track configuration parameters, you can get the space position sample accuracy, pose sample accuracy, script execution running speed, and script execution running acceleration.
Parameters	
Return value	Success: (0 , ( xyz_interval, rpy_interval, vel, acc)) xyz_interval: Space position acquisition speed rpy_interval: Orientation capture accuracy vel: Script execution running speed acc: Script execution running acceleration Failed: Others

## 4.6.3 Set trajectory sample mode

Function	set_traj_sample_mode(mode, filename)
Description	Set trajectory sample mode.
Parameters	mode: Control mode, True means starting data collection, False means ending data

	collection. filename: The name of the file where data are stored.
<b>Return value</b>	Success: (0,) Failed: Others

## 4.6.4 Get trajectory sample state

<b>Function</b>	<b>get_traj_sample_status()</b>
<b>Description</b>	Get trajectory sample state. Note: It is not allowed to turn on the data collection switch again during the data collection process.
<b>Parameters</b>	
<b>Return value</b>	Success: (0,sample_status),sample_status: Data status, True means data are being collected, False means data collection has been finished. Failed: Others

## 4.6.5 Get exist trajectory file name

<b>Function</b>	<b>get_exist_traj_file_name ()</b>
<b>Description</b>	Get exist trajectory file name
<b>Parameters</b>	
<b>Return value</b>	Success: (0,) Failed: Others

## 4.6.6 Rename exist trajectory file name

<b>Function</b>	<b>rename_traj_file_name (src, dest)</b>
<b>Description</b>	Rename exist trajectory file name
<b>Parameters</b>	src: Source file name dest: The target file name, the length of the file name cannot exceed 100 characters, the file name cannot be empty, the target file name does not support Chinese
<b>Return value</b>	Success: (0,) Failed: Others

Sample Code:

```

1. import jkrc                #import module
2. robot = jkrc.RC("192.168.2.226")  #returns a robot object
3. robot.login()
4. robot.rename_traj_file_name("\\home\\src', '\\home\\dst')
5. robot.logout() #exit

```

## 4.6.7 Remove the trajectory file in the controller

<b>Function</b>	<b>remove_traj_file(filename)</b>
<b>Description</b>	Remove the trajectory file in the controller
<b>Parameters</b>	filename: The name of the file to be deleted



<b>Return value</b>	Success: (0,) Failed: Others
---------------------	---------------------------------

Sample Code:

```
1. import jkrc                #import module
2. robot = jkrc.RC("192.168.2.226") #returns a robot object
3. robot.login()
4. robot.remove_traj_file('test')
5. robot.logout() #exit
```

## 4.6.8 Generate the trajectory execution script

<b>Function</b>	<b>generate_traj_exe_file(filename)</b>
<b>Description</b>	Generate the trajectory execution script
<b>Parameters</b>	filename: The filename of data
<b>Return value</b>	Success: (0, ) Failed: Others

## 4.7 Robot kinematics

### 4.7.1 Convert Rpy to rotation matrix

<b>Function</b>	<b>rpy_to_rot_matrix(rpy = [rx,ry,rz])</b>
<b>Description</b>	Convert Rpy to rot matrix
<b>Parameter</b>	rpy: rpy parameters to be converted [rx,ry,rz]
<b>Return value</b>	Success: (0, rot_matrix). rot_matrix is a 3X3 rotation matrix Failed: Others

### 4.7.2 Convert rotation matrix to rpy

<b>Function</b>	<b>rot_matrix_to_rpy(rot_matrix)</b>
<b>Description</b>	Covert Rot matrix to rpy
<b>Parameter</b>	rot_matrix: Rot matrix data to be converted
<b>Return value</b>	Success: (0, rpy). rpy is a tuple, whose length is 3. The expression of rpy is (rx, ry, rz). Failed: Others

### 4.7.3 Convert quaternion to rotation matrix

<b>Function</b>	<b>quaternion_to_rot_matrix (quaternion = [w,x,y,z])</b>
<b>Description</b>	Convert Quaternion to rot matrix

<b>Parameter</b>	quaternion: Quaternion data to be converted
<b>Return value</b>	Success: (0, rot_matrix). rot_matrix is a 3*3 rotation matrix Failed: Others

## 4.7.4 Kine inverse

<b>Function</b>	<b>kine_inverse(ref_pos, cartesian_pose)</b>
<b>Description</b>	Calculate the kine inverse of the specified pose under the current tool, current installation angle, and current user coordinate frame settings
<b>Parameter</b>	ref_pos: Reference joint position for kine inverse cartesian_pose: Cartesian space pose value
<b>Return value</b>	Success: (0, joint_pos) joint_pos is a tuple with 6 elements (j1, j2, j3, j4, j5, j6), J1, J2, J3, J4, J5, and j6 represent the Angle values from joint 1 to joint 6 respectively Failure: Others

## 4.7.5 Kine forward

<b>Function</b>	<b>kine_forward(joint_pos)</b>
<b>Description</b>	Calculate the pose value of the specified joint position under the current tool, current installation angle and current user coordinate frame settings
<b>Parameter</b>	joint_pos: Joint space position
<b>Return value</b>	success: (0, Cartesian_pose), where Cartesian_pose is a tuple containing 6 elements (x,y,z,rx,ry,rz), with x,y,z,rx,ry,rz representing the pose value of robot tool end Failed: Others

Sample Code:

```
"Kine forward"
1. import jkrc
2. robot = jkrc.RC("192.168.2.64") #returns a robot object
3. robot.login() #login
4. ret = robot.get_joint_position()
5. if ret[0] == 0:
6.     print("the joint position is :",ret[1])
7. else:
8.     print("some things happend,the errcode is: ",ret[0])
9. joint_pos = ret[1]
10. robot.kine_forward(joint_pos) #Kine forward
11. robot.logout() #exit
```

## 4.7.6 Convert rotation matrix to quaternion

<b>Function</b>	<b>rot_matrix_to_quaternion(rot_matrix)</b>
<b>Description</b>	Rot matrix to quaternion
<b>Parameter</b>	rot_matrix: 3x3 Rot matrix to be converted
<b>Return value</b>	Success: (0, quaternion). quaternion is a tuple, whose length is 4. The expression of quaternion is (w, x, y, z). Failed: Others

Sample Code:

```

1. import jkrc
2. robot = jkrc.RC("192.168.2.160")
3. robot.login()
4. ret = robot.get_tcp_position()
5. print(ret)
6. rpy = [ret[1][3], ret[1][4], ret[1][5]]#get rpy
7. ret = robot.rpy_to_rot_matrix(rpy)#convert rpy to rot matrix
8. print(ret)
9. rot_matrix = ret[1]#get rot matrix
10. ret = robot.rot_matrix_to_rpy(rot_matrix)#convert rot matrix to rpy
11. print(ret)
12. ret = robot.rot_matrix_to_quaternion(rot_matrix)# convert rot matrix to quaternion
13. print(ret)
14. quaternion = ret[1]
15. ret = robot.quaternion_to_rot_matrix(quaternion)# convert rot matrix to quaternion
16. print(ret)
17. robot.logout()

```

## 4.8 Robot Servo Mode

### 4.8.1 Robot servo move enable

<b>Function</b>	<b>servo_move_enable(enable)</b>
<b>Description</b>	Robot servo move enable
<b>Parameter</b>	enable :TRUE means to enter the servo move control mode, FALSE means to quit the mode
<b>Return value</b>	Success: (0,) Failed: Others

### 4.8.2 Robot joint servo move extension

<b>Function</b>	<b>servo_j(joint_pos, move_mode)</b>
-----------------	--------------------------------------

<b>Description</b>	Joint move control mode
<b>Parameter</b>	<p>Please note the following items for the robot joint move control mode:</p> <ul style="list-style-type: none"> <li>(a) Before using this interface the user needs to call <code>servo_move_enable(True)</code> first to enter the position control mode</li> <li>(b) This command is generally used in trajectory planning in university research.</li> <li>(c) When users use this mode to control the robot motion, the controller planner will not be involved in the motion interpolation, and the position command will be sent to the servo directly. Therefore users need to do the trajectory planning by themselves. Otherwise the robot motion effectiveness can be poor, like violent shaking, which can not meet the user's expectation.</li> <li>(d) Since the control cycle time of the controller is 8ms, it is recommended that the user should send the command with a period of 8ms too, and continuously. There will be no effect if the command is sent only once. In case of a poor network, the command can be sent with a period less than 8ms.</li> <li>(e) The upper limit on the Jaka robot joint speed is 180 degrees per second. If the joint speed exceeds this limit due to the joint angle that is sent, this command will then fail. For example, if the joint angle that is sent is [1.5,0.5,0.5,0.5,0.5,0.5] (here the unit is degree) and the sending period is 8ms, thus <math>1.5/0.008 = 187.5</math> degrees per second, which exceeds the upper limit on the joint speed. Then the command will be invalid.</li> <li>(f) After using this command, the user needs to use <code>servo_move_enable(False)</code> to exit the position control mode.</li> <li>(g) There is a big difference between this command and the aforementioned <code>joint_move()</code>, which interpolation is processed by controller, and the user does not need to care about it. When using <code>servo_j</code> command, users need to make trajectory planning in advance. Otherwise the effect will be poor and can not meet the expectation. <b>If there is no special requirement, it is recommended to use <code>joint_move</code> instead of <code>servo_j</code> on robot joint move control.</b></li> </ul>
<b>Parameters</b>	<p><code>joint_pos</code>: target robot joint move position</p> <p><code>move_mode</code> specified move mode: 0 for absolute move, 1 for incremental move</p>
<b>Return value</b>	<p>Success :(0,)</p> <p>Failed: Others</p>

Sample Code:

```

"using of servo_j"
1.  #-*- coding: utf-8 -*-
2.  import sys
3.  sys.path.append('D:\\vs2019ws\\PythonCtt\\PythonCtt')
4.  import time
5.  import jkrc
6.  ABS = 0      # absolute motion
7.  INCR = 1     # incremental motion
8.  Enable = True
9.  Disable = False
10. robot = jkrc.RC("192.168.2.160")#returns a robot object
11. robot.login()#login
12. robot.power_on() #power on
13. robot.enable_robot()
14. robot.servo_move_enable(Enable) #enter position control mode
15. print("enable")
16. for i in range(200):
17.     robot.servo_j(joint_pos =[0.001,0,0,0,0,0.001],move_mode = INCR)#
18. for i in range(200):
19.     robot.servo_j(joint_pos =[-0.001,0,0,0,0,-0.001],move_mode = INCR)
20. robot.servo_move_enable(Disable)# exit position control mode
21. print("disable")
22. robot.logout() #exit

```

## 4.8.3 Robot joint servo move extension

Function	<code>servo_j_extend(joint_pos, move_mode, setp_num)</code>
Description	<p>(a) Please note the following items for the robot joint move control mode:</p> <p>(b) Before using this interface the user needs to call <code>servo_move_enable(True)</code> first to enter the position control mode</p> <p>(c) This command is generally used in trajectory planning in university research.</p> <p>(d) When users use this mode to control the robot motion, the controller planner will not be involved in the motion interpolation, and the position command will be sent to the servo directly. Therefore users need to do the trajectory planning by themselves. Otherwise the robot motion effectiveness can be poor, like violent shaking, which can not meet the user's expectation.</p> <p>(e) Since the control cycle time of the controller is 8ms, it is recommended that the user should send the command with a period of 8ms too, and continuously. There will be no effect if the command is sent only once. In case of a poor network, the command can be sent with a period less than 8ms.</p> <p>(f) The upper limit on the Jaka robot joint speed is 180 degrees per second. If the joint speed exceeds this limit due to the joint angle that is sent, this command will become invalid. For example, if the joint angle that is sent is [1.5,0.5,0.5,0.5,0.5,0.5] (here the unit is degree) and the sending period is 8ms, thus <math>1.5/0.008 = 187.5</math> degrees per second, which exceeds the upper limit on the joint speed. Then the command will be invalid.</p> <p>(g) After using this command, the user needs to use <code>servo_move_enable(False)</code> to exit the position control mode.</p> <p>(h) There is a big difference between this command and the aforementioned <code>joint_move()</code>, which interpolation is processed by controller, and the user does not need to care about it. When using <code>servo_j</code> command, users need to make trajectory</p>

	planning in advance. Otherwise the effect will be poor and can not meet the expectation. If there is no special requirement, it is recommended to use joint_move instead of servo_j on robot joint move control.
<b>Parameters</b>	joint_pos: target robot joint move position move_mode specified move mode: 0 for incremental move, 1 for absolute move step_num: multiplying period, servo_j move period is step_num*8ms, where step_num>=1
<b>Return value</b>	Success: (0,) Failed: Others

## 4.8.4 Cartesian space servo mode

<b>Function</b>	<b>servo_p(cartesian_pose, move_mode)</b>
<b>Description</b>	<p>Please note the following items for the robot Cartesian space servo mode:</p> <ul style="list-style-type: none"> <li>(a) Before using this interface the user needs to call servo_move_enable(True) first to enter the position control mode</li> <li>(b) This command is generally used in trajectory planning in university research.</li> <li>(c) When users use this mode to control the robot motion, the controller planner will not be involved in the motion interpolation, and after the controller kine inverse is calculated, the position command will be sent to the servo directly. Therefore users need to do the trajectory planning himself. Otherwise the robot motion effectiveness can be poor, like violent shaking, which cannot meet users' expectation.</li> <li>(d) Since the control cycle time of the controller is 8ms, it is recommended that the user should send the command with a period of 8ms too, and continuously. There will be no effect if the command is sent only once. In case of a poor network, the command can be sent with a period less than 8ms.</li> <li>(e) The upper limit on the Jaka robot joint speed is 180 degrees per second. If the joint speed exceeds this limit due to the position that is sent, this command will become invalid.</li> <li>(f) After using this command, the user needs to use servo_move_enable(False) to exit the position control mode.</li> <li>(g) There is a big difference between this command and the aforementioned linear_move(), which interpolation is processed by controller, and the user does not need to care about it. When using <b>servo_p</b> command, users need to make trajectory planning in advance. Otherwise the effect will be poor and can not meet the expectation. <b>If there is no special requirement, it is recommended to use linear_move instead of servo_p on robot Cartesian space move control.</b></li> </ul>
<b>Parameters</b>	Cartesian_pose: Target robot Cartesian space move position. move_mode: Specified move mode, 0 for absolute move, 1 for incremental move
<b>Return value</b>	Success: (0,) Failed: Others

### Sample Code:

'''using of servo\_p'''

```

1. # -*- coding: utf-8 -*-
2. import sys
3. sys.path.append('D:\\vs2019ws\\PythonCtt\\PythonCtt')
4. import time
5. import jkrc
6. PI=3.1415926
7.
```

```

8. ABS = 0      # absolute motion
9. INCR = 1     # incremental motion
10. Enable = True
11. Disable = False
12.
13. robot = jkrc.RC("192.168.2.160")#returns a robot object
14. robot.login()#login
15. robot.power_on() #power on
16. robot.enable_robot()
17. joint_pos=[PI/3,PI/3,-PI/3,PI/4,PI/4,0]
18. robot.joint_move(joint_pos,ABS,True,1)
19. robot.servo_move_enable(Enable) # enter position control mode
20. print("enable")
21. for i in range(200):
22.     robot.servo_p(cartesian_pose = [1, 0, 0, 0, 0, 0],move_mode = INCR)
23. for i in range(200):
24.     robot.servo_p(cartesian_pose = [-1,0, 0, 0, 0, 0],move_mode = INCR)
25. robot.servo_move_enable(Disable)# exit position control mode
26. print("disable")
27. robot.logout() #exit

```

## 4.8.5 Robot Cartesian space servo move extension

Function	<code>servo_p_extend(cartesian_pose, move_mode, step_num)</code>
Description	<p>(a) Please note the following items for the robot Cartesian space servo mode:</p> <p>(b) Before using this interface the user needs to call <code>servo_move_enable(True)</code> first to enter the position control mode</p> <p>(c) This command is generally used in trajectory planning in university research.</p> <p>(d) When users use this mode to control the robot motion, the controller planner will not be involved in the motion interpolation, and after the controller kine inverse is calculated, the position command will be sent to the servo directly. Therefore users need to do the trajectory planning himself. Otherwise the robot motion effectiveness can be poor, like violent shaking, which cannot meet users' expectation.</p> <p>(e) Since the control cycle time of the controller is 8ms, it is recommended that the user should send the command with a period of 8ms too, and continuously. There will be no effect if the command is sent only once. In case of a poor network, the command can be sent with a period less than 8ms.</p> <p>(f) The upper limit on the Jaka robot joint speed is 180 degrees per second. If the joint speed exceeds this limit due to the position that is sent, this command will become invalid.</p> <p>(g) After using this command, the user needs to use <code>servo_move_enable(False)</code> to exit the position control mode.</p> <p>(h) There is a big difference between this command and the aforementioned <code>linear_move()</code>, which interpolation is processed by controller, and the user does not need to care about it. When using <code>servo_p</code> command, users need to make trajectory planning in advance. Otherwise the effect will be poor and can not meet the expectation. If there is no special requirement, it is recommended to use <code>linear_move</code> instead of <code>servo_p</code> on robot Cartesian space move control.</p>
Parameters	Cartesian_pose: Target robot Cartesian space move position

	move_mode:Specify the movement mode,0 is absolute movement,1 is incremental movement step_num: multiplying period, servo_p move period is step_num*8ms, where step_num>=1
<b>Return value</b>	Success: (0,) Failed: Others

## 4.8.6 None filters in SERVO mode

<b>Function</b>	<b>servo_move_use_none_filter()</b>
<b>Description</b>	It is not allowed to use any filter in the robot SERVO mode. This command cannot be set in the SERVO mode. It can be set only after exiting the SERVO mode.
<b>Parameters</b>	
<b>Return value</b>	Success: (0,) Failed: Others

Sample Code:

```
1. import jkrc                #import module
2. robot = jkrc.RC("192.168.2.226") #returns a robot object
3. robot.login()
4. robot.servo_move_use_none_filter()
5. robot.logout() #exit
```

## 4.8.7 Use joint first-order low pass filter in SERVO mode

<b>Function</b>	<b>servo_move_use_joint_LPF(cutoffFreq)</b>
<b>Description</b>	Use Robot joint space first-order low-pass filter in SERVO mode. This command cannot be set in the SERVO mode. It can be set only after exiting the SERVO mode.
<b>Parameters</b>	cutoffFreq: First-order low-pass filter cut-off frequency.
<b>Return value</b>	Success: (0,) Failed: Others

Sample Code:

```
1. import jkrc                #import module
2. robot = jkrc.RC("192.168.2.226") #returns a robot object
3. robot.login()
4. robot.servo_move_use_joint_LPF(0.5)
5. robot.logout() #exit
```

## 4.8.8 Use joint nonlinear filter in SERVO mode

<b>Function</b>	<b>servo_move_use_joint_NLF(max_vr, max_ar, max_jr)</b>
<b>Description</b>	Use Robot joint space nonlinear filter in SERVO mode. This command can not be set in SERVO mode. It can be set only after exiting the SERVO mode.
<b>Parameters</b>	max_vr: The upper limit of Cartesian space orientation change speed (absolute value) °/s max_ar: The upper limit of accelerated speed of Cartesian space orientation change speed (absolute value)°/s^2 max_jr: The upper limit value of jerk (absolute value) of Cartesian space orientation change speed °/s^3



<b>Return value</b>	Success: (0, Failed: Others
---------------------	--------------------------------

Sample Code:

```
1. import jkrc                #import module
2. robot = jkrc.RC("192.168.2.226") #returns a robot object
3. robot.login()
4. robot.servo_move_use_joint_NLF(max_vr=2, max_ar=2, max_jr=4)
5. robot.logout() #exit
```

## 4.8.9 Use Cartesian space nonlinear filter in SERVO mode

<b>Function</b>	<b>servo_move_use_carte_NLF(max_vp, max_ap, max_jp, max_vr, max_ar, max_jr)</b>
<b>Description</b>	Use Cartesian space nonlinear filter in the Robot Servo mode. This command can not be set in the SERVO mode. It can be set only after exiting the SERVO mode.
<b>Parameters</b>	max_vp: The upper limit (absolute value) of the move command speed in Cartesian space mm/s max_ap: The upper limit (absolute value) of the move command acceleration in Cartesian space mm/s^2 max_jp: The upper limit (absolute value) of the move command accelerated acceleration in Cartesian space mm/s^3 max_vr: The upper limit of Cartesian space orientation change speed (absolute value) °/s max_ar: The upper limit of accelerated speed of Cartesian space orientation change speed (absolute value)°/s^2 max_jr: The upper limit value of jerk (absolute value) of Cartesian space orientation change speed °/s^3
<b>Return value</b>	success: (0, Failed: Others

Sample Code:

```
1. import jkrc                #import module
2. robot = jkrc.RC("192.168.2.226") #returns a robot object
3. robot.login()
4. robot.servo_move_use_carte_NLF(max_vp=2, max_ap=2, max_jp=4,max_vr=2, max_ar=2, max_jr=4)
5. robot.logout() #exit
```

## 4.8.10 Use joint multi-order mean filter in SERVO mode

<b>Function</b>	<b>servo_move_use_joint_MMF(max_buf, kp, kv, ka)</b>
<b>Description</b>	Use joint space multi-order mean filter in the Robot SERVO mode. This command can not be set in the SERVO mode. It can be set only after exiting the SERVO mode.
<b>Parameters</b>	max_buf: The buffer size of the mean filter. kp: Acceleration filter factor. kv: Speed filter factor ka: Position filter factor
<b>Return value</b>	Success: (0, Failed: Others

Sample Code:

```
1. import jkrc #import module
2. robot = jkrc.RC("192.168.2.226") #returns a robot object
3. robot.login()
4. robot.servo_move_use_joint_MMF(max_buf=20 , kp=0.2 , kv=0.4 ,ka=0.2)
5. robot.logout() #exit
```

## 4.8.11 Set the speed foresight parameters in SERVO mode

Function	<code>servo_speed_foresight (max_buf, kp)</code>
<b>Description</b>	Set the speed foresight parameters in SERVO mode
<b>Parameters</b>	max_buf: The buffer size of the mean filter. kp: Acceleration filter factor.
<b>Return value</b>	Success: (0,) Failed: Others

## 4.9 Force Control Robot Extensions

Additional force control sensors need to be loaded on the end of the tool for the following interfaces to work

### 4.9.1 Set sensor brand

Function	<code>set_torsensor_brand(sensor_brand)</code>
<b>Description</b>	Set the sensor brand. The number input represents the corresponding sensor brand, with the optional values of 1, 2 and 3, representing the different F/T sensors, respectively.
<b>Parameters</b>	sensor_brand: The number corresponding to the sensor brand
<b>Return value</b>	Success: (0,) Failed: Others

Sample Code:

```
1. import jkrc #import module
2. robot = jkrc.RC("192.168.2.165") #returns a robot object
3. robot.login()
4. robot.set_torsensor_brand(1) #1 for SONY Semiconductor; 2 for Bosch Sensortec; 3 for ST Microelectronics
5. robot.logout() #exit
```

### 4.9.2 Get sensor brand

Function	<code>get_torsensor_brand()</code>
<b>Description</b>	Get the brand of the sensor currently being used. The numbers output represent the different sensor brands.
<b>Parameters</b>	
<b>Return value</b>	Success: (0,sensor_brand), where sensor_brand represents the sensor brand, with the optional values of 1, 2 and 3, representing the different F/T sensors, respectively. Failed: Others

Sample Code:

```
1. import jkrc #import module
2. robot = jkrc.RC("192.168.2.165") #returns a robot object
```

```

3. robot.login()
4. ret=robot.get_torsensor_brand()
5. if ret[0] == 1:
6.     print("the sensor_band is SONY Semiconductor")
7. elif ret[0] == 2:
8.     print("the sensor_band is BoschSensortec")
9. else:
10.    print("the sensor_band is ST Microelectronics")
11. robot.logout() #exit

```

## 4.9.3 Turn on or turn off F/T sensor

<b>Function</b>	<b>set_torque_sensor_mode(sensor_mode)</b>
<b>Description</b>	Turn on or turn off the F/T sensor currently being used.
<b>Parameters</b>	sensor_mode: The sensor working mode, 0 means turning off the F/T sensor, 1 means turning on the F/T sensor.
<b>Return value</b>	Success: (0,) Failed: Others

## 4.9.4 Set compliance control parameters

<b>Function</b>	<b>set_admit_ctrl_config(axis, opt, ftUser, ftReboundFK, ftConstant, ftNormalTrack)</b>
<b>Description</b>	When set the robot compliance control, you can set such parameters as joint axis numbers, compliance direction, damping force, rebound force, constant force and normal tracking.
<b>Parameters</b>	axis: represents the axis number of Cartesian space, with a value range of 0 to 5, representing the corresponding directions of fx, fy, fz, mx, my and mz, respectively. opt: The compliance direction, 0 for turning off, 1 for turning on. ftUser: The damping force, indicating that how much force the user needs to apply to make the robot move along a certain direction at the maximum speed. ftReboundFK: The rebound force, indicating the ability of the robot to return to its initial state. ftConstant: The constant force, all of which are set to 0 when manual operation. ftNormalTrack: The normal tracking, all of which are set to 0 when manual operation.
<b>Return value</b>	Success: (0,) Failed: Others

## 4.9.5 Start to identify the tool end payload

<b>Function</b>	<b>start_torq_sensor_payload_identify(joint_pos)</b>
<b>Description</b>	Start to identify the tool end payload, and input a tuple of 6 elements, representing the 6 joint angles of end position.
<b>Parameters</b>	joint_pos: the end position for the F/T sensor to do automatic payload identification, corresponding to 6 joint angles
<b>Return value</b>	Success: (0,) Failed: Others

## Sample Code:

```
1.  #-*- coding: utf-8 -*-
2.  import sys
3.  #sys.path.append('D:\\vs2019ws\\PythonCtt\\lib')
4.  import time
5.  import jkrc
6.  PI = 3.1415926
7.
8.  robot = jkrc.RC("10.5.5.100")#returns a robot object
9.  ret = robot.login()#login
10. ret = robot.power_on()
11. ret = robot.enable_robot()
12. robot.set_torsenosr_brand(2)
13. robot.set_torque_sensor_mode(1)
14. robot.set_compliant_type(1, 1)
15. print("inint sensor comple")
16. print("ready to run")
17. ret = robot.get_joint_position()
18. joint_pos_origin = ret[1]
19. joint_pos = ret[1]
20. print(joint_pos)
21. joint_pos[3] += PI / 4
22. if (joint_pos[3] > 265 * 180 / 180):
23.     joint_pos[3] -= PI/2
24. joint_pos[4] += PI / 4
25. if (joint_pos[4] > 320 * 180 / 180):
26.     joint_pos[4] -= PI/2
27. joint_pos[5] += PI / 4
28. if (joint_pos[5] > 265 * 180 / 180):
29.     joint_pos[5] -= PI
30. print(joint_pos)
31. ret = robot.start_torq_sensor_payload_identify(joint_pos)
32. time.sleep(1)
33. flag = 1
34. while (1 == flag):
35.     ret = robot.get_torq_sensor_identify_staus()
36.     print(ret)
37.     time.sleep(1)
38.     flag = ret[1]
39. print("identity_finish")
40. ret = robot.get_torq_sensor_payload_identify_result()
41. print(ret)
42. ret = robot.set_torq_sensor_payload()
43. print(ret)
44. ret = robot.get_torq_sensor_payload_identify_result()
45. print(ret)
46. robot.joint_move(joint_pos_origin,0,1,10)
47. print("back")
48. robot.logout() #exit
```

## 4.9.6 Get end payload identification status

<b>Function</b>	<b>get_torq_sensor_identify_status()</b>
<b>Description</b>	Get end payload identification status
<b>Parameters</b>	identify_status: The identification status, 0 means identification completed, 1 means identification uncompleted, 2 means identification failed.
<b>Return value</b>	Success: (0,identify_status) Failed: Others

## 4.9.7 Get end payload identification result

<b>Function</b>	<b>get_torq_sensor_payload_identify_result()</b>
<b>Description</b>	Get the end load identification result, and input load quality and centroid coordinates
<b>Parameters</b>	mass: payload mass, unit: kg centroid: load centroid coordinates [x, y, z], unit: mm
<b>Return value</b>	Success: (0,) Failed: Others

## 4.9.8 Set sensor end load

<b>Function</b>	<b>set_torq_sensor_tool_payload (mass, centroid)</b>
<b>Description</b>	Set the sensor end load, and input load quality and centroid coordinates.
<b>Parameters</b>	mass: payload mass, unit: kg centroid: load centroid coordinates [x, y, z], unit: mm
<b>Return value</b>	Success: (0,) Failed: Others

### Sample Code:

```

1. import jkrc                               #import module
2. robot = jkrc.RC("192.168.2.226")          #returns a robot object
3. robot.login()
4. robot.set_torq_sensor_tool_payload(mass= 1, centroid =[10,10,0])
5. robot.logout() #exit

```

## 4.9.9 Get sensor end load

<b>Function</b>	<b>get_torq_sensor_tool_payload ()</b>
<b>Description</b>	Get sensor end load quality and centroid coordinates.
<b>Parameters</b>	
<b>Return value</b>	Success: (0,(mass,centroid)), mass: The load quality, unit: kg centroid: load centroid coordinates [x, y, z], unit: mm Failed: Others

## 4.9.10 Force-control admittance enable control

Function	enable_admittance_ctrl (enable_flag)
Description	Force-control admittance enable control
Parameters	enable_flag: The flag, 0 means turning off force-control drag enable, 1 means turning on force-control admittance enable.
Return value	Success: (0,) Failed: Others

### Sample Code:

```

1.  # -*- coding: utf-8 -*-
2.  import sys
3.  #sys.path.append('D:\\vs2019ws\\PythonCtt\\lib')
4.  import time
5.  import jkrc
6.  PI=3.1415926
7.
8.  robot = jkrc.RC("10.5.5.100")#returns a robot object
9.  ret = robot.login()#login
10. ret = robot.power_on()
11. ret = robot.enable_robot()
12. robot.set_torsenosr_brand(2)
13. robot.set_torque_sensor_mode(1)
14. robot.set_compliant_type(1, 1)
15. print("inint sensor comple")
16. print("ready to run")
17. #Set compliance control parameters
18. ret = robot.set_admit_ctrl_config(0, 0, 20, 5, 0, 0)
19. ret = robot.set_admit_ctrl_config(1, 0, 20, 5, 0, 0)
20. ret = robot.set_admit_ctrl_config(2, 1, 20, 10, 0, 0)
21. ret = robot.set_admit_ctrl_config(3, 0, 20, 5, 0, 0)
22. ret = robot.set_admit_ctrl_config(4, 0, 20, 5, 0, 0)
23. ret = robot.set_admit_ctrl_config(5, 0, 20, 5, 0, 0)
24. #Set force control drag enable, 1 means on and 0 means off
25. ret = robot.enable_admittance_ctrl(1)
26. print("enable_admittance_ctrl open! ")
27. print("input any word to quit:")
28. a = input()
29. ret = robot.enable_admittance_ctrl(0)
30. ret = robot.set_admit_ctrl_config(2, 0, 20, 5, 0, 0)
31. robot.set_torque_sensor_mode(0)
32. robot.logout() #exit

```

## 4.9.11 Set the force control type and sensor initial state

Function	set_compliant_type(sensor_compensation, compliance_type)
Description	Set the force control type and sensor initial state
Parameters	sensor_compensation: Turn on sensor compensation enable flag. 1 means turning on initialization, and 0 means no initialization

	compliance_type: The force control type. 0 means not using any kind of compliance control method, 1 means using constant compliance control, and 2 means using speed compliance control
<b>Return value</b>	Success: (0,) Failed: Others

Sample Code:

```
import jkrc #import module
robot = jkrc.RC("192.168.2.226") #returns a robot object
robot.login()
robot.set_compliant_type(1,1)
robot.logout() #exit
```

## 4.9.12 Get the force control type and sensor initial state

<b>Function</b>	<b>get_compliant_type()</b>
<b>Description</b>	Get the force control type and sensor initial state
<b>Parameters</b>	
<b>Return value</b>	Success: (0, sensor_compensation, compliance_type) sensor_compensation: Turn on sensor compensation enable flag. 1 means turning on initialization, and 0 means no initialization compliance_type: The force control type. 0 means not using any kind of compliance control method, 1 means using constant compliance control, and 2 means using speed compliance control Failed: Others

## 4.9.13 Get the force-control compliance control parameters

<b>Function</b>	<b>get_admit_ctrl_config()</b>
<b>Description</b>	By getting the force-control compliance control parameters, you can get the compliance direction, damping force, rebound force, constant force and normal tracking which are corresponding to the 6 joints.
<b>Parameters</b>	
<b>Return value</b>	Success: (0, [[opt, ftUser, ftReboundFK, ftConstant, ftNormalTrack], .....]) opt: The compliance direction, with an optional value range of 1 to 6, corresponding to the directions of fx, fy fz, mx, my and mz, respectively, and 0 means no check. ftUser: The damping force, indicating that how much force the user needs to apply to make the robot move along a certain direction at the maximum speed. ftReboundFK: The rebound force, indicating the ability of the robot to return to its initial state. ftConstant: The constant force, all of which are set to 0 when manual operation. ftNormalTrack: The normal tracking, all of which are set to 0 when manual operation. Failed: Others

## 4.9.14 Set the F/T sensor IP address

<b>Function</b>	<b>set_torque_sensor_comm(type, ip_addr, port)</b>
<b>Description</b>	Set the F/T sensor IP address.
<b>Parameters</b>	type: The sensor type ip_addr: The sensor IP address port: The port number
<b>Return value</b>	Success: (0,) Failed: Others

## 4.9.15 Get the F/T sensor IP address

<b>Function</b>	<b>get_torque_sensor_comm()</b>
<b>Description</b>	Get the F/T sensor IP address.
<b>Parameters</b>	
<b>Return value</b>	Success: (0,ip_addr),ip_addr: The sensor IP address. Failed: Others

## 4.9.16 Disable the torque control

<b>Function</b>	<b>disable_force_control ()</b>
<b>Description</b>	Disable the torque control
<b>Parameters</b>	
<b>Return value</b>	Success: (0,) Failed: Others

## 4.9.17 Set speed compliance control parameters

<b>Function</b>	<b>set_vel_compliant_ctrl (level, rate1, rate2, rate3, rate4)</b>
<b>Description</b>	Set the speed compliance control parameters. There are 3 speed compliance control levels and 4 rate levels.
<b>Parameters</b>	level: The compliance control levels which are divided into level 1, 2, and 3 1, 2, 3 rate1: Rate level 1 rate2: Rate level 2 rate3: Rate level 3 rate4: Rate level 4 Note: Relations between rate levels: $0 < \text{rate4} < \text{rate3} < \text{rate2} < \text{rate1} < 1$ ; (a) When level = 1, only the values of rate1 and rate 2 can be set, and the values of rate 3 and rates 4 are all zero (b) When level =2, only the values of rate1, rate 2 and rate 3 can be set, and the value of rate 4 is zero (c) When level = 3, all the values of rate 1, rate 2, rate 3 and rate 4 can be set



<b>Return value</b>	Success: (0,) Failed: Others
---------------------	---------------------------------

## 4.9.18 Set the compliance control torque conditions

<b>Function</b>	<b>set_compliance_condition (fx, fy, fz, tx, ty, tz)</b>
<b>Description</b>	Set the compliance control torque conditions.
<b>Parameters</b>	fx: the force along X-axis, unit: N fy: the force along Y-axis, unit: N fz: the force along Z-axis, unit: N tx: the torque around X-axis, unit: Nm ty: the torque around Y-axis, unit: Nm tz: the torque around Z-axis, unit: Nm
<b>Return value</b>	Success: (0,) Failed: Others

## 4.9.19 Set the low-pass filter parameters of the force control

<b>Function</b>	<b>set_torque_sensor_filter(HZ);</b>
<b>Description</b>	Set condition of compliance control torque
<b>Parameters</b>	HZ: low-pass filter parameters, unit: HZ
<b>Return value</b>	Success: (0,) Failed: Others

## 4.9.20 Get the low-pass filter parameters of the force control

<b>Function</b>	<b>get_torque_sensor_filter();</b>
<b>Description</b>	Set condition of compliance control torque
<b>Parameters</b>	HZ: low-pass filter parameters, unit: HZ
<b>Return value</b>	Success: (0, HZ) Failed: Others

## 4.9.21 Set the sensor limit parameter configuration of the sensor

<b>Function</b>	<b>set_torque_sensor_soft_limit(fx, fy, fz, tx, ty, tz);</b>
<b>Description</b>	Set condition of compliance control torque
<b>Parameters</b>	fx: force along x-axis, unit: N fy: force along the y-axis, unit: N fz: force along the z-axis, unit: N tx: torque around the x-axis, unit: Nm ty: torque around y-axis, unit: Nm tz: torque around z-axis, unit: Nm
<b>Return value</b>	Success: (0,) Failed: Others

## 4.9.22 Get the sensor limit parameter configuration of the sensor

<b>Function</b>	<code>get_torque_sensor_soft_limit();</code>
<b>Description</b>	Set condition of compliance control torque
<b>Parameters</b>	
<b>Return value</b>	Success: (0,(fx,fy,fz,tx,ty,tz)) fx: force along x-axis, unit: N fy: force along the y-axis, unit: N fz: force along the z-axis, unit: N tx: torque around the x-axis, unit: Nm ty: torque around y-axis, unit: Nm tz: torque around z-axis, unit: Nm Failed: Others

## 4.9.23 Zero calibration of sensor

<b>Function</b>	<code>Zero_end_sensor();</code>
<b>Description</b>	Zero calibration of end sensor
<b>Parameters</b>	None
<b>Return value</b>	Success: (0,) Failed: Others

## 4.9.24 Get tool drive state

<b>Function</b>	<code>Get_tool_drive_state();</code>
<b>Description</b>	Get the tool drive coordinate system
<b>Parameters</b>	None
<b>Return value</b>	Success: (0,enable_flag,drive_state) Enable_flag: 0 is to turn off force control dragging, 1 is to turn it on, drive_stat is whether the current state of dragging triggers singularity point, speed, joint limit warning Failed: Others

## 4.9.25 Get the force sensor's coordinate system in drag mode

<b>Function</b>	<code>get_tool_drive_frame();</code>
<b>Description</b>	Get the tool drive coordinate system
<b>Parameters</b>	None
<b>Return value</b>	Success: (0,ftFrame) ftFrame: 0 Tool 1 World Failed: Others

## 4.9.26 Set the force sensor's coordinate system in drag mode

<b>Function</b>	<code>set_tool_drive_frame(ftFrame);</code>
<b>Description</b>	set the tool drive coordinate system
<b>Parameters</b>	None
<b>Return value</b>	Success: (0,ftFrame)

	ftFrame: 0 Tool 1 World Failed: Others
--	--

## 4.9.27 Get fusion drive sensitivity

<b>Function</b>	get_fusion_drive_sensitivity_level();
<b>Description</b>	Get the fusion drive sensitivity level
<b>Parameters</b>	None
<b>Return value</b>	Success: (0,level) Level: sensitivity level, value:0-5, 0 means not turned on Failed: Others

## 4.9.28 Set fusion drive sensitivity

<b>Function</b>	Set_fusion_drive_sensitivity_level(level);
<b>Description</b>	Set the fusion drive sensitivity level
<b>Parameters</b>	Level: sensitivity level, value:0-5, 0 means not turned on
<b>Return value</b>	Success: (0,) Failed: Others

## 4.9.29 Get motion limit (singularity and joint limit) warning range

<b>Function</b>	get_motion_limit_warning_range(warningRange);
<b>Description</b>	Get the warning range of motion limit (singularity and joint limit)
<b>Parameters</b>	None
<b>Return value</b>	Success: (0,warningRange) WarningRange: the range that warnings would happen Failed: Others

## 4.9.30 Set motion limit (singularity and joint limit) warning range

<b>Function</b>	set_motion_limit_warning_range(warningRange);
<b>Description</b>	set the warning range of motion limit (singularity and joint limit)
<b>Parameters</b>	WarningRange: the range that warnings would happen
<b>Return value</b>	Success: (0,) Failed: Others

## 4.9.31 Get compliant speed limit

<b>Function</b>	get_compliant_speed_limit();
<b>Description</b>	Get the compliant speed limit
<b>Parameters</b>	None
<b>Return value</b>	Success: (0,vel,angularvel) Vel: linear velocity limit, mm/s Angularvel: angular velocity limit, rad/s Failed: Others

## 4.9.32 Set compliant speed limit

<b>Function</b>	<b>set_compliant_speed_limit(vel, angularvel);</b>
<b>Description</b>	set the compliant speed limit
<b>Parameters</b>	Vel: linear velocity limit, mm/s Angularvel: angular velocity limit, rad/s
<b>Return value</b>	Success: (0,) Failed: Others

## 4.9.33 Get torque reference center

<b>Function</b>	<b>get_torque_ref_point();</b>
<b>Description</b>	Get the torque reference center
<b>Parameters</b>	None
<b>Return value</b>	Success: (0,refpoint) Refpoint: 0 torque sensor center, 1 TCP center Failed: Others

## 4.9.34 Set torque reference center

<b>Function</b>	<b>set_torque_ref_point(refpoint);</b>
<b>Description</b>	set the torque reference center
<b>Parameters</b>	Refpoint: 0 torque sensor center, 1 TCP center
<b>Return value</b>	Success: (0,) Failed: Others

## 4.9.35 Get end sensor sensitivity

<b>Function</b>	<b>get_end_sensor_sensitivity_threshold ();</b>
<b>Description</b>	Get the end sensor sensitivity threshold
<b>Parameters</b>	
<b>Return value</b>	Success: (0,data) Fx: force on x axis, unit: N Fy: force on y axis, unit: N Fz: force on z axis, unit: N Tx: torque around x axis, unit: Nm Ty: torque around y axis, unit: Nm Tz: torque around z axis, unit: Nm Failed: Others

## 4.9.36 Set end sensor sensitivity

<b>Function</b>	<b>set_end_sensor_sensitivity_threshold (fx, fy, fz, tx, ty, tz);</b>
<b>Description</b>	set the end sensor sensitivity threshold
<b>Parameters</b>	Fx: force on x axis, unit: N Fy: force on y axis, unit: N Fz: force on z axis, unit: N Tx: torque around x axis, unit: Nm Ty: torque around y axis, unit: Nm Tz: torque around z axis, unit: Nm An array of six element, the larger the value is, the less sensitive the sensor is
<b>Return value</b>	Success: (0,data) Failed: Others

## 4.10 FTP Services

## 4.10.1 Initialize FTP

<b>Function</b>	<b>init_ftp_client()</b>
<b>Description</b>	Initialize the FTP client, establish connection with control cabinet, and import and export program and track
<b>Parameters</b>	none
<b>Return value</b>	Success: (0,) Failed: Others

## 4.10.2 Close FTP client

<b>Function</b>	<b>close_ftp_client()</b>
<b>Description</b>	Close FTP client
<b>Parameters</b>	none
<b>Return value</b>	success: (0,) Failed: Others

## 4.10.3 Interrogate the directory of controller FTP

<b>Function</b>	<b>get_ftp_dir(remotedir, type);</b>
<b>Description</b>	Interrogate controller directory
<b>Parameters</b>	remotedir: The controller internal folder name type: 0 for file and folder, 1 for file, 2 for folder
<b>Return value</b>	Success: (0,ret), where ret is a string Failed: Others

### Sample Code:

```

1. import jkrc
2. robot = jkrc.RC("192.168.2.26")
3. robot.login()
4. dir= "/program/"
5. #login controller, you need to convert 192.168.2.26 into your own controller IP
6. robot.init_ftp_client()
7. result = robot.get_ftp_dir("/program/", 0)
8. print(result)
9. robot.close_ftp_client()
10. robot.logout()

```

## 4.10.4 Download FTP file

<b>Function</b>	<b>download_file(local, remote, opt)</b>
<b>Description</b>	Download the file or folder from Robot control cabinet FTP to your local directory, and Interrogate track "/track/" and script program "/program/"
<b>Parameters</b>	remote: the controller internal filename absolute path. Whether the folder name should

	<p>be ended with a "\" or "/" should depend on the system.</p> <p>For example, a path of "/program/test/test.jks" for a single file, or a path of "/program/test/" for a folder</p> <p>local: the absolute filename path to download the file to local directory</p> <p>opt: 1 for single file, 2 for folder</p>
<b>Return value</b>	<p>Success: (0,)</p> <p>Failed: Others</p>

Sample Code: Download the program folder on the ftp to the program folder on the desktop

```

1. import jkrc
2. robot = jkrc.RC("192.168.2.26")#VMmodel
3. robot.login()
4. remote = "/program/"
5. local= "C:\\Users\\Administrator\\Desktop\\program\\track\\"
6. robot.init_ftp_client()
7. result = robot.download_file(local, remote, 2)
8. print(result)
9. robot.close_ftp_client()
10. robot.logout()

```

## 4.10.5 Upload files to FTP

<b>Function</b>	<b>upload_file(local, remote, opt)</b>
<b>Description</b>	Upload files with specified types and names from your local directory to controller
<b>Parameters</b>	<p>remote: the absolute filename path to upload the file to controller. Whether a folder name should be ended with a "\" or "/" should depend on the system</p> <p>local: the local filename absolute path</p> <p>opt: 1 for single file, 2 for folder</p>
<b>Return value</b>	<p>Success: (0,)</p> <p>Failed: Others</p>

Sample Code: Upload all files and folders from the lxxpro folder on the desktop to the program/folder of the ftp

```

1. import jkrc
2. robot = jkrc.RC("192.168.2.26")#VMmodel
3. robot.login()
4. remote = "/program/"
5. local= "C:\\Users\\Administrator\\Desktop\\lxxpro\\"
6. robot.init_ftp_client()
7. result = robot.upload_file(local, remote, 2)
8. print(result)
9. robot.close_ftp_client()
10. robot.logout()

```

## 4.10.6 Rename FTP files

<b>Function</b>	<b>upload_file(local, remote, opt)</b>
<b>Description</b>	Rename controller files with specified types and names
<b>Parameters</b>	<p>remote: the controller internal filename absolute path. Whether the folder name should be ended with a "\" or "/" should depend on the system.</p>

	des: name of target files renamed opt: 1 for single file, 2 for folder. When renaming files, all files in the folder will be renamed to be used by /track/ easily
<b>Return value</b>	Success: (0,) Failed: Others

Sample Code: Rename all files and folders in the ftp's lxxpro folder to lxx

```

1. import jkrc
2.
3. robot = jkrc.RC("192.168.2.26")#VMmodel
4. robot.login()
5. remote = "/lxxpro/"
6. des = "lxx"
7. robot.init_ftp_client()
8. result = robot.rename_ftp_file(remote, des, 2)
9. print(result)
10. robot.close_ftp_client()
11. robot.logout()

```

## 4.10.7 Delete FTP files

<b>Function</b>	<b>del_ftp_file( remote, opt)</b>
<b>Description</b>	Upload files with specified types and names from controller to your local directory
<b>Parameters</b>	remote: the controller internal filename absolute path. Whether the folder name should be ended with a "\" or "/" should depend on the system. opt: 1 for single file, 2 for folder
<b>Return value</b>	Success: (0,) Failed: Others

Sample Code: Be careful, the demo will delete all programs ! ! ! !

```

1. import jkrc
2.
3. robot = jkrc.RC("192.168.2.26")#VMmodel
4. robot.login()
5. dir= "/program/"
6. robot.init_ftp_client()
7. result = robot.del_ftp_file("/program/", 2)
8. print(result)
9. robot.close_ftp_client()
10. robot.logout()

```

## 5.Feedback and Error Correct

If there is an inaccurate description or error in the document, the reader is kindly requested to point the finger at criticism. If you find any questions or comments you would like to make during your reading, you can send an email to [support@jaka.com](mailto:support@jaka.com) and our colleagues will reply.

